WebCenter 14

Installation Guide





Contents

1. Copyright Notice	4
2. Overview of a WebCenter Installation	6
3. Hardware and Software Requirements	7
4. WebCenter 14 Installation Tips	10
5. Installation Checklist	12
5.1 Installation Checklist for Fresh Installation	12
5.2 Installation Checklist for Upgrade	13
6. CHILI-WebCenter Connection	16
6.1 Share between CHILI and WebCenter	16
6.2 Requirements for Reverse Proxy for CHILI Server	16
7. Pre-Installation Steps	17
8. Installing WebCenter	
8.1 Overview of the Installation Procedure	21
8.2 Install SQL Server 2012 Express Edition on the Database Server	
8.3 Install the Application Server Components	23
8.3.1 Install ArtiosCAD on the Application Server	
8.3.2 Activate the Licenses	
8.3.3 Install the WebCenter Application Server	
8.4 Run the Database Schema Scripts on the Application Server	
8.5 Install the Web Server	
8.5.1 Uninstall IIS on the Web Server if Configured Incorrectly	
8.5.2 Install IIS on the Web Server.	
8.5.3 Extend the Upload Limitation	
8.5.4 Disable 32 Bit Applications	
8.5.5 Install the WebCenter Web Server	
8.6 Install the On-Board Graphics Engine (OBGE) on the Application Server	
8.6.1 How to perform the	
8.6.2 How to install the prerequisite components	
•	
9. Testing WebCenter	35
10. Configuring WebCenter	
10.1 Configure the OBGE	
10.1.1 Create a Container	
10.1.2 Create a JDF Hot Folder (Access Point) for WebCenter	

10.1.3 Improve the Performance of View Data Generation	37
10.2 Configuring the E-Mail Notifications	38
10.2.1 Configure E-Mail Notification	38
10.3 Configure WebCenter for Use with ArtiosCAD Enterprise	39
10.3.1 Configuring BLOBs	39
10.3.2 Step 2 - Optionally Running the Board Importer Batch F	ile40
10.3.3 Step 3 - Loading the ArtiosCAD Defaults	41
10.3.4 Configuration in the WebCenter User Interface	42
10.4 Secure your WebCenter Site with SSL	43
10.4.1 Secure the WebCenter Web Server with SSL	43
10.4.2 Install SSL Certificates on the Workflow Production Serv	/er51
10.5 Install Certificates for LDAPS on the Application Server	55
10.6 Integrate WebCenter with a Workflow Production Server	58
10.6.1 Understanding WebCenter Integration	58
10.7 Expose WebCenter to the Internet	61
10.7.1 Register a Domain Name	61
10.7.2 Contact Your ISP to Set Up an A Record	62
10.7.3 Move the Web Server Inside the Demilitarized Zone (DN	1Z)62
10.7.4 Configure IIS to Receive Traffic	63
11. Deploying WebCenter	64
12. Localizing WebCenter	66
12.1 Understanding Localization in WebCenter	66
12.2 How to Install Custom Translations	66
13. The Help System	68
14. Upgrading from WebCenter	70
14.1 Prepare for the Upgrade	70
14.1.1 Prerequisites for the Upgrade	70
14.1.2 Prepare for the Upgrade on the Application Server	
14.1.3 Prepare for the Upgrade on the Web Server	71
14.2 Upgrade WebCenter	72
14.2.1 Remove WebCenter	72
14.2.2 Install WebCenter 14	
14.2.3 Upgrade the OBGE	73
14.2.4 Configure WebCenter 14	74
15. Uninstalling WebCenter	75



1. Copyright Notice

© Copyright 2015 Esko Software BVBA, Gent, Belgium

All rights reserved. This material, information and instructions for use contained herein are the property of Esko Software BVBA. The material, information and instructions are provided on an AS IS basis without warranty of any kind. There are no warranties granted or extended by this document. Furthermore Esko Software BVBA does not warrant, guarantee or make any representations regarding the use, or the results of the use of the software or the information contained herein. Esko Software BVBA shall not be liable for any direct, indirect, consequential or incidental damages arising out of the use or inability to use the software or the information contained herein.

The information contained herein is subject to change without notice. Revisions may be issued from time to time to advise of such changes and/or additions.

No part of this document may be reproduced, stored in a data base or retrieval system, or published, in any form or in any way, electronically, mechanically, by print, photoprint, microfilm or any other means without prior written permission from Esko Software BVBA.

This document supersedes all previous dated versions.

PANTONE[®], PantoneLIVE and other Pantone trademarks are the property of Pantone LLC. All other trademarks or registered trademarks are the property of their respective owners. Pantone is a wholly owned subsidiary of X-Rite, Incorporated. [®] Pantone LLC, 2014. All rights reserved.

This software is based in part on the work of the Independent JPEG Group.

Portions of this software are copyright $^{\odot}$ 1996-2002 The FreeType Project (www.freetype.org). All rights reserved.

Portions of this software are copyright 2006 Feeling Software, copyright 2005-2006 Autodesk Media Entertainment.

Portions of this software are copyright ©1998-2003 Daniel Veillard. All rights reserved.

Portions of this software are copyright ©1999-2006 The Botan Project. All rights reserved.

Part of the software embedded in this product is gSOAP software. Portions created by gSOAP are Copyright ©2001-2004 Robert A. van Engelen, Genivia inc. All rights reserved.

Portions of this software are copyright ©1998-2008 The OpenSSL Project and ©1995-1998 Eric Young (eay@cryptsoft.com). All rights reserved.

This product includes software developed by the Apache Software Foundation (http://www.apache.org/).

Adobe, the Adobe logo, Acrobat, the Acrobat logo, Adobe Creative Suite, Illustrator, InDesign, PDF, Photoshop, PostScript, XMP and the Powered by XMP logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.

Microsoft and the Microsoft logo are registered trademarks of Microsoft Corporation in the United States and other countries.

SolidWorks is a registered trademark of SolidWorks Corporation.

Portions of this software are owned by Spatial Corp. 1986 2003. All Rights Reserved.

JDF and the JDF logo are trademarks of the CIP4 Organisation. Copyright 2001 The International Cooperation for the Integration of Processes in Prepress, Press and Postpress (CIP4). All rights reserved.

The Esko software contains the RSA Data Security, Inc. MD5 Message-Digest Algorithm.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems in the U.S. and other countries.

Part of this software uses technology by BestTM Color Technology (EFI). EFI and Bestcolor are registered trademarks of Electronics For Imaging GmbH in the U.S. Patent and Trademark Office.

Contains PowerNest library Copyrighted and Licensed by Alma, 2005 – 2007.

All other product names are trademarks or registered trademarks of their respective owners.

Correspondence regarding this publication should be forwarded to:

Esko Software BVBA

Kortrijksesteenweg 1095

B - 9051 Gent

info.eur@esko.com



2. Overview of a WebCenter Installation

The WebCenter installation procedure involves a number of different steps that need to be performed in a specific order.

The table below shows a list of the steps required to install WebCenter either for the first time or as an upgrade:

Step	Description
1	Check the Requirements and perform pre-installation work: • Hardware and Software Requirements on page 7
	• Pre-Installation Steps on page 17
2	 Installing WebCenter on page 21: Install SQL Server 2012 Express Edition on the Database Server on page 22 Install ArtiosCAD on the Application Server on page 23 Install the WebCenter Application Server on page 25 Install the WebCenter Web Server on page 30 Start the WebCenter Services on page 31 Install the On-Board Graphics Engine (OBGE) on the Application Server on page 33
3	Testing WebCenter on page 35
4	Configuring WebCenter on page 36: 1. Configure the OBGE on page 36 2. Configuring the E-Mail Notifications on page 38 3. Secure your WebCenter Site with SSL on page 43 4. Install Certificates for LDAPS on the Application Server on page 55 5. Integrate WebCenter with a Workflow Production Server on page 58 6. Expose WebCenter to the Internet on page 61

3. Hardware and Software Requirements



Attention: For the latest hardware and software requirements, please check the Esko website.

WebCenter employs three distinct servers, a **Web Server**, an **Application Server**, and a **Database Server**.

It also has a **FileStore** and an **On-Board Graphics Engine (OBGE)**, which is used to generate view data.

New IT Requirements for WebCenter 14

WebCenter 14 runs on 64-bit operating systems only. Only Windows Server 2008 R2 or later are supported.

In case the Viewer service is installed with the option **External**, 3 extra ports will need to be opened between the Application and Web Server: 11099, 12500 and 14444.

Entry Level (Two Server Systems Required)

WebCenter Entry Level requirements are based on an activity with 10 concurrent users active at any time and less than 100 users in the system. Customers with higher performance needs should refer to the Advanced Level requirements.

In the Entry Level setup, the installation of the **Application Server** and **Database Server** is combined onto a single machine. The **OBGE** and the **FileStore** are on the Application Server.

For reasons of security the **Web Server** is always on its own dedicated computer and placed in a demilitarized zone (DMZ). We recommend the use of hardware firewalls for creating the DMZ.

Advanced Level (Three or More Server Systems Required)

When the WebCenter Entry Level cannot meet the load requirements of the system, it is possible to scale the system.

For reasons of security the Web Server will always be a separate computer in a DMZ.

Each of the other WebCenter components (**Application Server**, **Database Server**, **FileStore** and **OBGE**) can be offloaded onto separate machines in different combinations.

For Advanced Level installations, it is recommended to choose the **Advanced** Installer option to allow more custom configuration, and to choose **Extra Large** for the Deployment Size.

Requirements

Category	Entry Level (Standard - < 100 users)	Advanced Level (Extra Large - 100+ users)
Operating System	Microsoft Windows Server 2008 Service Pack 2 or better	Microsoft Windows Server 2008 Service Pack 2 or better
	Note: Microsoft Windows Server 2000 and 2003 are no longer supported.	Note: Microsoft Windows Server 2000 and 2003 no longer supported.

Category	Entry Level (Standard - < 100 users)	Advanced Level (Extra Large - 100+ users)
Processor - Application Server with On-Board Graphics Engine	x86-64 compatible processor (Intel or AMD), minimum 8 cores	x86-64 compatible processor (Intel or AMD), minimum 12 cores, 6 + 6 per 100 users
Processor - All other WebCenter Servers	x86-64 compatible processor (Intel or AMD), minimum 4 cores	x86-64 compatible processor (Intel or AMD), minimum 6 cores, 2 + 4 per 100 users, 2 + 6 per 100 users for separate DB server
RAM Memory (Application Server with DB and OBGE)	12 GB or more	32 GB or more
RAM Memory (Application Server with OBGE)	12 GB or more	24 GB or more
RAM Memory (Application Server)	12 GB or more	18 GB or more
RAM Memory (Separate Database Server)	12 GB or more	minimum 12 GB or the size of the DB (whichever is larger), add 8 GB per 100 users
RAM Memory (Web Server)	6 GB or more	12 GB or more
Available hard disk space - Application Server	50 GB or more	200 GB or more
Available hard disk space - Web Server	10 GB or more	10 GB or more
Available hard disk space - Database Server	20 GB or more	60 GB or more
Display	1024 x 768 pixels, 16-bit color minimum	1024 x 768 pixels, 16-bit color minimum
Media drives - Application Server	DVD-ROM or connection to networked DVD-ROM drive	DVD-ROM or connection to networked DVD-ROM drive
Media drives - Web Server	DVD-ROM or connection to networked DVD-ROM drive	DVD-ROM or connection to networked DVD-ROM drive
Network (all servers)	10/100/1000 Base-T Ethernet, TCP/IP v4 protocol, TCP/IP v6 protocol	10/100/1000 Base-T Ethernet, TCP/IP v4 protocol, TCP/IP v6 protocol
Database software	Microsoft SQL Server 2008 (Workgroup Edition, Standard Edition, Enterprise Edition)	Microsoft SQL Server 2008 (Workgroup Edition, Standard Edition, Enterprise Edition)
	Microsoft SQL 2008 R2 (Express Edition (SP2), Workgroup	 Microsoft SQL 2008 R2 (Workgroup Edition, Standard Edition, Enterprise Edition)

Category	Entry Level (Standard - < 100 users)	Advanced Level (Extra Large - 100+ users)
	Edition, Standard Edition, Enterprise Edition) Microsoft SQL Server 2012 (Express Edition, Workgroup Edition, Standard Edition, Enterprise Edition) Note: Microsoft SQL Server 2005 (Express Edition, Workgroup Edition, Standard Edition, Enterprise Edition) is still supported, but we recommend using Microsoft SQL Server 2008 (R2) or 2012. Microsoft SQL Server 2000 and MSDE are no longer supported. Oracle 10g or 11g Enterprise Edition Note: Oracle 8i and 9i are no longer supported. Oracle 12c is not yet supported.	 Microsoft SQL Server 2012 (Workgroup Edition, Standard Edition, Enterprise Edition) Note: Microsoft SQL Server 2005 (Workgroup Edition, Standard Edition, Enterprise Edition) is still supported, but we recommend using Microsoft SQL Server 2008 (R2) or 2012. Microsoft SQL Server 2000 and MSDE are no longer supported. Oracle 10g or 11g Enterprise Edition Note: Oracle 8i and 9i are no longer supported. Oracle 12c is not yet supported.

Notes

- The Database Server needs 10 GB of free space on the partition containing the database files to allow for database expansion.
- The Application Server is the default location for uploaded files (also known as the FileStore).

Ensure it has at least 50 GB of available hard drive space, and that **the disk space is expandable**. Alternatively, find a network location with expandable disk space to specify as the file storage location when loading the Application Server.

- The Web, Application and Database Servers must have the same OS language, regional setting (such as English (United States)), and time zone setting.
- You must be able to download and install Java applets automatically to use the Java Viewer.
 If Java is installed but a red X appears in the browser when launching the Viewer, consult your system administrator to see if a firewall or proxy blocks Java downloads.
- If you are using a Microsoft Hyper-V hypervisor virtual machine, do not install both the WebCenter Web Server and the Esko Licensing software on this virtual machine.



4. WebCenter 14 Installation Tips

Licenses

• WebCenter 14 Licenses

If you are planning an installation of WebCenter 14, you will need to request WebCenter 14 licenses. The old WebCenter 10.x or 12.x licenses will not work anymore.

Advanced License

Since WebCenter 14.0.2, large installations from 50 concurrent users require a WebCenter Advanced License. A special 'advanced' variant of the concurrent user licenses is also needed in this case.

Note:

From WebCenter 14.0.2 onwards, the maximum number of regular concurrent licenses that can be installed is set to 50 instead of 30. If you install more than 50 regular licenses for concurrent usage, the licenses will be truncated to 50.

You will see a warning message informing you that the number of concurrent licenses exceeds the maximum and that the number of available licenses will be truncated to 50.

To install more than 50 concurrent licenses, you need a WebCenter Advanced License.

Reporting License

Since WebCenter 12, there is a new feature license for enabling the customizable part of the new Reporting functionality.

Network Licensing Tool

For WebCenter 14, you need to install ArtiosCAD Enterprise 14.0en, this installation includes the required Network License Manager.

Server Configuration

Ports

The required ports for WebCenter 12 and later are 1099, 2500, 4444 and 3873.

In case the Viewer service is installed with the option External (new in WebCenter 14), 3 extra ports will need to be opened between the Application and Web Server: 11099, 12500 and 14444.

Database

The database shipped as default with WebCenter 14 is MSSQL 2012 Express.

OBGE 14

In case the OBGE 14 is installed on the Web Server (not recommended), make sure to stop the EG Web Server service before starting Tomcat.

Note that Automation Engine 14 no longer uses Hot Folders explicitely, but you can now configure the FileStore JDF Hot Folder by creating an Access Point which is described in *Create a JDF Hot Folder (Access Point) for WebCenter*.

IIS

If you move to WebCenter 14 from WebCenter 12.x, leaving the installation of IIS intact, a change to IIS may be needed. In IIS, go to Application Pools and open the Advanced Settings for DefaultAppPool. Make sure that 'Enable 32-Bit Applications' is set to 'False'. After changing the setting, click 'Recycle...'.

• Simple or Advanced Installation

Since WebCenter 14, it is possible to choose between a Simple or Advanced installation. If the Advanced installation mode is selected, the memory size allocated for the JBoss service on the Application Server and the TomCat service on the Web Server need to be specified. Choosing the Extra Large option is recommended for servers that are expected to experience a heavy load and high concurrent user access.

Internal or External Viewer

In case of an Advanced installation, the Viewer service can be set to Internal or External. Selecting External will make the Viewer service run as a separate process. Note that choosing External requires extra ports to be opened between the Application and Web Server: 11099, 12500 and 14444.

Database user

In case of an Advanced installation, it is possible to set a custom password for the **webcenter** database user.

Boards

Previously, in older versions of ArtiosCAD, the Boards needed to be installed by running a .bat file after the WebCenter installation. Since ArtiosCAD 14.0, you can install the Boards automatically during the ArtiosCAD installation, this is highly recommended.

Servicing

• Admin Console

In WebCenter 14, it is possible to inspect JBoss by going to: http://yourhost:8086/adminconsole.

Services

In WebCenter 14, you will only see the following WebCenter services:

- JBoss
- Tomcat
- CAD-X

The App-X and Search Crawler services are no longer needed since WebCenter 12.

In order to run the services interactively, open the command prompt and go to ..\Esko \Artios\WebCenter\ApplicationServer\NAMEOFSERVICE\bin for each service, and run wcr_nameofservice_srv_cmdrun.bat. For example: C:\Esko\Artios\WebCenter \ApplicationServer\JBoss\bin\wcr_jboss_srv_cmdrun.bat.



5. Installation Checklist

The Installation Checklist can be used as a tool alongside the rest of the Installation Guide to ensure you completed all the necessary steps during the installation. There are two versions, the first one can be used for a fresh installation, the second one can be used in case of an upgrade.

5.1 Installation Checklist for Fresh Installation

This checklist can be used whilst performing a fresh installation of WebCenter (meaning WebCenter was not installed on the same machine(s) before).

Please complete the Installation Checklist in the same order as listed here.

Not	Note: Do not run this installation from a network share.				
	On the Application Server Install ArtiosCAD Enterprise located on the WebCenter DVD. For WebCenter 14.0, ArtiosCAD Enterprise 14.0 build 124 or newer is required. Install License Server Components from the ArtiosCAD Installer.				
	Activate Network Licenses via the Network License Manager:				
	□ WebCenter 14.0 (Standard or Advanced) □ CAD Engine 14.0 □ OBGE 14.0 □ Optional licenses Reserve TCP Ports. If you are going to use MS SQL Server (no prerequisites for Oracle): □ Install MS .NET framework 3.5 (run the script from the WebCenter DVD to install it). Or, if you use a MS SQL Database on Windows Server 2008 r2 without access to the Internet: □ Install MS .NET framework 4.5 (run the script from the WebCenter DVD to install it).				
	Note: For servers with Windows Server 2012 or with access to the Internet, this will happen automatically.				
	☐ Install the SQL Server 2012 SP1 Express Edition Database engine for WebCenter. ☐ Always install SQL Management Studio on the Application Server.				
	Create the local BGSYSTEM Windows user (run the script from the WebCenter DVD to create it).				
	Create the FileStore folder and share it as a network folder with all rights enabled for the BGSYSTEM user.				
	Install the Application Server component of WebCenter; build the Database schema and REBOOT .				

		Install the OBGE from the Automation Engine DVD by selecting the option: Install Automation Engine 14.0 as On Board Graphics Engine (OBGE) for WebCenter .
		Configure the Access Point (formerly known as Hot Folder) in the Automation Engine Pilot to generate view files for graphic files.
		On the Web Server
		Install and configure IIS 7 (Windows Server 2008 r2) or IIS 8 (Windows Server 2012) on the Web Server.
		Make sure that Enable 32-bit programs in IIS is set to False .
		Increase the upload limit in the request filtering.
		Install the Web Server component of WebCenter and REBOOT.
		On the Application Server Since WebCenter 12.1, services are started automatically. Verify that the following services are started:
		□ JBoss
		□ CAD-X
		☐ Application Monitor
		On the Web Server Verify that the following services have been started:
		☐ TomCat
		☐ Application Monitor
		Connect to WebCenter in your browser: http://[WebServer]/WebCenter_Inst.
		☐ Username: admin. Password: [blank].
		☐ Change password.
		Install the ArtiosCAD Defaults in English and Import the Boards (directly from the ArtiosCAD Defaults Installer).
50		
5.21	ns —	tallation Checklist for Upgrade
		s checklist can be used whilst performing an upgrade installation of WebCenter 14.0 (meaning an er version/build of WebCenter was installed on the same machine(s) before).
	Plea	ase complete the Installation Checklist in the same order as listed here.
	Not	e: Do not run this installation from a network share.
		On the Web and Application Server
		Stop all WebCenter services.
		On the Application Server
		Backup the whole $\Begin{array}{l} {\tt Backup the whole} \\ {\tt WebCenter} \\ {\tt ApplicationServer folder (make a copy, do not move it) and backup the following:} \\ \end{array}$
		□ FileStore



	☐ Database
	☐ Email configuration (if you upgrade from a WebCenter < 12)
	On the Web Server
	Backup the whole\WebCenter\WebServer folder (make a copy, do not move it).
	Uninstall the old version of WebCenter on both Application and Web Server and REBOOT both servers after uninstall.
	Remove all WebCenter instances in IIS on the Web Server.
	On the Application Server
	Reserve TCP Ports.
	Upgrade to ArtiosCAD Enterprise 14.0 located on the WebCenter DVD. For WebCenter 14.0, ArtiosCAD Enterprise 14.0 build 124 or newer is required.
	Upgrade the Network License Manager via the Install License Server Components from the ArtiosCAD installer.
	Upgrade WebCenter WebCenter Licenses and dependants (CAD Engine and OBGE) to 14.0.
	In case of still using MSDE 2000 Database, use the migration tool on the WebCenter 12.X DVD to migrate from MSDE 2000 to SQL 2005 Express (oldest Database engine supported for upgrades).
	If you are using MS SQL Server, make sure that SQL Management Studio is always installed on the Application Server.
	Install the Application Server component of WebCenter using the existing FileStore and Database. DO NOT REBOOT YET
	Re-apply email customization on the Application Server.
	Build the Database schema if this was not done during the installation.
	REBOOT
	Update to Automation Engine OBGE 14 and configure the Access Point (formerly known as Hot Folder) in the Automation Engine Pilot to generate view files for graphic files.
	On the Web Server
	Install the Web Server component of WebCenter.
	Make sure that Enable 32-bit programs in IIS is set to False.
	To be able to use Excel based lists from the Web Server, install a 64-bit driver (see link on the WebCenter DVD). DO NOT REBOOT YET
	Re-deploy WebCenter Instance(s) and re-apply customizations.
	REBOOT
	On the Application Server
	Since WebCenter 12.1, services are started automatically. Verify that the following services are started:
	□JBoss
	□ CAD-X
	Application Monitor
	On the Web Server
П	Verify that the following services have been started:

☐ TomCat
☐ Application Monitor
Connect to WebCenter in your browser: http://[WebServer]/WebCenter_Inst.
Username: admin. Password: [old admin password].
Install or merge the ArtiosCAD Defaults in English and Import the Boards (directly from the
 ArtiosCAD Defaults Installer).



6. CHILI-WebCenter Connection

6.1 Share between CHILL and WebCenter

A **CHILI share** is used to temporarily hold the files while registering them to the **CHILI server**. WebCenter will create a sub folders corresponding to the CHILI environments in this CHILI share root folder.

Note: The share must have :

- read and write permissions for WebCenter 'BGSYSTEM' user.
- read permissions for CHILI server.

6.2 Requirements for Reverse Proxy for CHILI Server

IIS ports accessing CHILI over the WebCenter web server should be :

- 80 for IIS http
- 443 for IIS https

The https ports must have a security certificate attached to it in order to be able to work with Web Server.

Note: The best practise is to install a properly signed certificate, matching the CHILI server hostname (NOT the tricked hostname) on the CHILI server. In this scenario, the validation of the SSL certificate will be smooth when the WebCenter Application Server makes a connection to it.

Alternatively, you may use a self-signed certificate. However, these are NOT supported for the WebCenter Web Server. You may get SSL validation errors when the WebCenter Application Server tries to connect to the CHILI server due to this.

As a work-around, use the WebCenter LDAP CertInstall tool:

- Go to the <Installation Directory>\ApplicationServer\LDAP.
- Run the following command:

CertInstall.bat <chiliserver>:443

- Select the right certificate to install by entering a digit.
- Restart the JBoss.

This will solve the SSL validation problems.

7. Pre-Installation Steps

Execute the following steps to make sure you have all the required information and materials for the installation.

1. Log on to all servers as a local administrator user.



Attention:

Logging on as DOMAIN ADMIN does not ensure you are a member of the local Administrators group.

Verify that the account you are using to log on to each machine belongs to the local Administrators group before you continue!

- 2. Make sure you use **compatible** software versions:
 - a) Gather the installation media on CD or DVD for ArtiosCAD, WebCenter, and Automation Engine (OBGE).
 - b) Only very specific versions of ArtiosCAD, WebCenter, and Automation Engine (OBGE) work with each other.

You CANNOT assume that a new version or build of one product will be compatible with older versions of the other products.

Software	Version	Build
ArtiosCAD		
WebCenter		
Automation Engine		

- 3. Check the licenses for the Esko installers:
 - a) Gather Graphics and CAD licenses.
 - b) If this is an upgrade, you will need to ask for updated license files.
 - c) Check the license files against your software order.

Verify that the licenses have the correct number of users, the expiration date if applicable, and the correct ArtiosCAD, WebCenter, and Automation Engine (OBGE) version information.

4. Gather the required **mail server** information:

Note:

The mail server must be on the same network as the WebCenter Application Server.

Also, ensure this mail server has a send-only e-mail account already created for specific use with WebCenter notifications (this usually requires creation of an account such as webcenter@mycompany.com).

Mail Server Information	Value
Mail Server Name	
Mail Server IP Address	
SMTP Port	
WebCenter Sender Address	
SMTP Authentication User Name	
SMTP Authentication Password	

5. Gather the required **database information** from the database administrator:

Database	Item	Value
SQL Server	server name	
	"sa" password	
	database instance name	
	database port (default is 1433)	
Oracle Server	server name	
	'sys' password	
	TNS name	
	database instance name	
	database port (default is 1527)	

- **6.** Ask the database administrator whether a custom password for the 'webcenter' database user will be required and if so, retrieve the expected target password for this database user.
- 7. Perform a Web Server health check:
 - a) We highly recommend not to begin the install with the Web Server inside the DMZ. It is best to **configure on a local LAN** first.

Get all applications installed, configured, and fully functional before moving the Web Server inside the DMZ. Otherwise any required troubleshooting will be difficult and will take longer than needed.

- b) Verify that **Internet Information Services (IIS)** is installed and its services are started: IISADMIN and W3SVC (World Wide Web Publishing).
- c) Make sure the **Server** service is running.
- 8. Test the mail server connection:

Note:

Ensure that you can use telnet commands and that its port is not blocked in any way.

Make sure you test this before starting the installation. IT Administrators often block the required SMTP ports.

- a) From the Application Server, open a command prompt.
- b) Use a telnet command with the following syntax: telnet <mail_server_name_or_ip> <smtp_port#>.

For example, my mail server name is mail.eskowebcenter1.com and my SMTP port is 25.

I would type: telnet mail.eskowebcenter1.com 25.

You are looking for a successful response (for example like the one below); a 220 response is good.

```
telnet mail.eskowebcenter1.com 25Trying 62.204.32.250...Connected to mail.eskowebcenter1.com (62.204.32.250).220 mail.eskowebcenter1.com Mail Server; Mon, 2 Jun 2014 11:26:40 EST
```

Type QUIT to exit the telnet command.

9. Make sure the **Server** service is running on the Application Server.

10.Check the Database Server:

- a) Ensure the correct database engine, version and service pack are installed. See section *Install SQL Server 2012 Express Edition on the Database Server*.
- b) For SQL Server 2008/2012 or Express 2008/2012 verify these configurations:
 - Must be configured to run in Mixed Mode for authentication;
 - Language/Character set of SQL Server must match the Operating System language;
 - TCP/IP must be enabled.
 - If a named instance is used, the SQL Server Browser must be set to start automatically (and must be running).
- c) This assumes that the system is protected by an external firewall.
- **11.**Check performance for all servers:
 - a) For all servers (Web, Application, Database), ensure Windows System Performance is set to **Adjust for Best Performance**:

Go to **Control Panel** > **System** > **Advanced** and select **Adjust for Best Performance** from the **Performance** list.

b) Ensure Control Panel > Automatic Updates is set to Download updates for me, but let me choose when to install.

Windows Updates have been known to interfere with WebCenter operation: some updates lock down ports and stop services related to web and internet.

It is your responsibility to test Microsoft updates before applying them to production servers.

c) Ensure Windows Firewall is disabled:

Go to **Control Panel > Network Connections**, right-click on the active network connection and choose **Properties**. On the **Advanced** tab, ensure **Internet Connection Firewall** is disabled.



d) Stop and temporarily disable virus software.

Temporarily stop virus services on the Web Server and the Application Server as they are known to interfere with the WebCenter installation script.

Only after the software is installed should you enable the virus software again.

8. Installing WebCenter

Installing WebCenter is a multi-step process spread over two or three servers depending on your configuration. We strongly recommend having three servers.

8.1 Overview of the Installation Procedure

This is a broad overview of the steps required to install WebCenter.

- 1. Perform the *Pre-Installation Steps* on page 17.
- 2. On the Database Server, optionally create a database called WebCenter4_0 if using Microsoft SQL Server. If you do not create the database at this point, it will be done by the WebCenter installer.

If using Oracle, we recommend that the SID (System Identifier) of the database be <code>WCenter</code>, but it can be anything; just make sure you know the exact name so you can enter it while loading WebCenter on the Application Server.

- 3. On the Application Server:
 - a) If using Microsoft SQL Server or SQL Server Express Edition, install Microsoft SQL Server Management Studio (if you have not done so already). This is provided as part of the MSSQL Express installer provided on the DVD. If you are using Oracle, it is advised to also install SQL Developer Studio, which can be downloaded from the Oracle web site.
 - b) Install ArtiosCAD.

Even if the Application Server already has a version of ArtiosCAD on it, you must load the version that came with WebCenter.

For more information on loading and configuring ArtiosCAD, refer to the installation instructions on its media.

- c) Activate the Licenses on page 24
- d) Install the WebCenter Application Server.
- 4. Run the Database Schema Scripts on the Application Server.

This is only required if the database schema scripts were not run automatically, or if the automatic run failed. Running the database schema scripts automatically is preferred. If needed, it is still possible to run the database scripts manually from the **Application Server**.

5. On the Web Server, install the WebCenter Web Server.

Reboot the Web Server machine if prompted.

- **6.** Start the WebCenter Services:
 - a) On the Application Server, start JBOSS and CAD-X.
 - b) On the Web Server, start Tomcat.



Note: These services are set to start automatically by the installer and will thus be started automatically after each machine reboot. If you prefer to start the services manually, you may set them to start manually by changing their properties in the **Services** applet via **Control Panel** > **Administrative Tools**.

Note: Since WebCenter 12 a new monitoring service is installed and started automatically. This service can be used by your WebCenter support agent for troubleshooting.

7. Install the On-Board Graphics Engine (OBGE) from the Automation Engine media. This will take about a half hour.

Note:

You must install the OBGE even if you are running a separate Automation Engine production server.

The OBGE will handle files uploaded through the WebCenter user interface, reducing the load on your Automation Engine production server.

WebCenter is now installed.

- 8. Log on the WebCenter web interface and:
 - a) Change the administrator password.
 - b) Configuring the E-Mail Notifications on page 38 if you will be using it.
- 9. Install the ArtiosCAD defaults.

See Loading the ArtiosCAD Defaults for details.

8.2 Install SQL Server 2012 Express Edition on the Database Server

Microsoft SQL Server 2012 Express Edition (supplied with WebCenter) is a free version of Microsoft SQL Server 2012 that can serve as the database engine for WebCenter.

To install it, use the **Install the SQL Server 2012 Express Edition database engine for WebCenter** link on the WebCenter installation media.

Following steps describe how to install the MSSQL Server 2012 Express database on a clean system:

- 1. When the SQL Server Installation Center launches, select the option New SQL Server standalone installation or add features to an existing installation.
- 2. If prompted, accept the License Terms and click Next.
- **3.** A quick check will be done and the installation will be prepared.
- 4. Select the Features you wish to install. If unsure, enable all except LocalDB.
- **5.** On the **Instance Configuration** screen, select **Named Instance** and name your instance **WEBCENTER**. You can also change the instance root directory if you want.
- **6.** On the **Server Configuration** screen, you can define separate accounts for each service, leave as default.
- 7. You can also specify your **Database Engine Collation**, leave as default.
- 8. On the **Database Engine Configuration** screen, choose the **Mixed Mode** authentication type.

- **9.** On the same screen, specify the **SQL Server system administrator (sa)** password. The default password is (Drupa2000), but you can enter a different one if desired.
- 10.On the Reporting Services Configuration screen, select Install and Configure and click Next.
- **11.**The system will now continue with the installation. The last screen shows that the installation process was completed successfully. You may be asked to restart the computer.
- **12.**If you now inspect your Programs, you should see **Microsoft SQL Server 2012** listed, along with other tools like **SQL Server Management Studio**.
- 13. Launch the SQL Server Management Studio to check the connection to the Database Engine.
- 14.In case it has not been created yet, add a new database named WebCenter4_0.
- **15.**Launch the **SQL Server Configuration Manager** to check the TCP/IP and SQL Server service statuses.
- **16.**Choose **SQL Server Network Configuration** > **Protocols for WEBCENTER** > , make sure **TCP/IP** is set to **Enabled** for **WEBCENTER**.
- **17.**In the **SQL Server Services** section, restart the **SQL Server** service. Also, make sure the **SQL Server Browser** service is running.

8.3 Install the Application Server Components

8.3.1 Install ArtiosCAD on the Application Server

- 1. Log on to the Application Server as a member of the local Administrators group.
- 2. Load the ArtiosCAD media that came with WebCenter.

Important:

Even if the Application Server already has a version of ArtiosCAD on it, you must load the version that came with WebCenter. In the case of WebCenter 14, you need ArtiosCAD Enterprise 14.0en build 124 or higher.

Make sure to also run the **Install Network License Components** installer from the **ArtiosCAD Installer**

In order for WebCenter to output PDF files, the ArtiosCAD PDF option must be purchased and then chosen when installing.

For more information on loading and configuring ArtiosCAD, refer to its installation instructions on the ArtiosCAD media.

3. In the Esko ArtiosCAD Setup window, click Install Esko ArtiosCAD 14.0en.

Depending on your system configuration prior to loading ArtiosCAD, the Microsoft Data Access Components and MSXML 6 may be copied to your system.

If the system prompts you to reboot, do so; the installation program will resume automatically when you log in after the system comes up again. Do not postpone rebooting if the system requests it.

- 4. The Esko ArtiosCAD 14.0en InstallShield Wizard opens.
 - a) In the **Licensing Method** screen, choose **Network Licenses**. Make sure the **Server** field contains the name of the Application Server (it should be filled in by default).



- b) In the **Setup Type** screen, choose **Typical** for a regular WebCenter installation, or **Advanced** if you will be working with ArtiosCAD Enterprise.
- c) In the Feature Selection screen, make sure PDF Import/Export is enabled.

Note: You will only see this screen when performing an **Advanced** setup to work with ArtiosCAD Enterprise.

d) In the **Advanced Options** screen, you can leave the default options selected. If you wish to change them please see the ArtiosCAD documentation for details.

Note: You will only see this screen when performing an **Advanced** setup to work with ArtiosCAD Enterprise.

e) In the **User Files Folder** screen, keep the default location for the storage of user files, or **Change** it if desired. If you change the location to another system, use a UNC locator (for example \\system2\designs) instead of a mapped drive letter.

Note: You will only see this screen when performing an **Advanced** setup to work with ArtiosCAD Enterprise.

- f) Click Install.
- g) Once the installation is complete, click Finish to close the installer.
- 5. If the system asks you to reboot, do so.

Note: You will need to perform extra configuration later to work with ArtiosCAD Enterprise.

Note: Since ArtiosCAD 14.0, you can install the Boards automatically during the ArtiosCAD Defaults installation, this is highly recommended. In case you do not choose to install the Boards during the ArtiosCAD installation, you will have to import them manually later.

Create a Detailed Installation Log

For Installation debugging and troubleshooting purposes, you can create a detailed installation log file for any Esko Installer programs. To do this:

Run setup using the following syntax: Path+program space /v"/I*v space path+logfilename

- For example: For ArtiosCAD installation from CD-ROM in my D:\ drive,
- Open a command prompt and Change to the D:\ drive
- Type: setup /v"/I*v c:\temp\ACsetup.log"

8.3.2 Activate the Licenses

If you have not done so already, install the **Network License Components** from the **ArtiosCAD Installer** first.

Activate your licenses using the Esko Network License Manager.

Note: To perform this task, consult the Network License Manager User Manual.

You need to activate:

your ArtiosCAD license,


your license for the OBGE (Automation Engine license).

8.3.3 Install the WebCenter Application Server

The Application Server components of WebCenter can be installed from a link on the installation media.

Before doing so, click the link on the DVD to **Create the local BGSYSTEM Windows user** in case this user was not created before.

- 1. Log on to the Application Server as a member of the local Administrators group.
- 2. Insert the WebCenter media into the media drive, and click **Software Installation** on the menu that appears at left, then **Install WebCenter 14**.
- 3. The setup wizard opens with a Welcome screen. Click Next.
- 4. In the License Agreement screen, read the agreement, and if you agree to it, select I accept the terms in the license agreement and click Next.
- 5. Select either Simple (default) or Advanced Installation. Keep Simple (default) selected unless you mean to specify non-default values for either Installation Size, Image Viewer Service or Database User management.
- 6. In the Custom Setup screen:



- a) Click the icon next to WebServer and select This feature will not be available.
- b) Click the icon next to **Application Server**, and select **This feature, and all subfeatures, will** be installed on local hard drive.
- c) If desired, click **Change** to change the installation folder.
- d) Click Next.



7. In the **WebCenter File Storage Folder** screen, choose the location where all data files uploaded to WebCenter will be stored (the **FileStore**).

Note: If you want to change the FileStore location, click **Change...** and browse to your desired location or enter a UNC address. Using a UNC location such as \\system\sharename \\FileStore is the most reliable option. The FileStore should be on a partition with **at least 50 GB of free space**.

Troubleshooting:

If the installer fails to create the FileStore, it will give you a message saying that you have to set it up manually.

Go to the folder that you will use as a FileStore (by default, C:\Esko\Artios\WebCenter\FileStore, or the location of your choice), and share it (typically to the user BGSYSTEM).

Click Next.

8. In the Web Server System screen, enter the name you will give to the Web Server and click Next.

Note: Once you have completed the installation and launched WebCenter, the Application Server must be able to **resolve the Web Server name you have entered here into an IP address**.

- 9. In the Database Configuration screen, enter your database information:.
 - a) Choose your Database program (Microsoft SQL Server or Oracle).
 - b) Enter the name of your Database Server in Database server system.
 - c) If you chose...
 - Microsoft SQL Server, enter your Database Instance Name. By default, this is WEBCENTER (using the SQL Server 2012 Express Edition installer on the WebCenter installation media created this instance).
 - Oracle, enter your Database System Identifier (SID).

Click Next when done.

10.A custom **webcenter** database user password can be set. In that case you will need to provide a password value. This screen will only be shown in case of an Application Server installation.

Note: This screen appears only for Advanced installation.

11.Choose between a Standard (default) and an Extra Large deployment. If Extra Large is selected, Tomcat and/or JBoss (depending on the server being installed) will be able to allocate 3 times more memory as is the case with a Standard installation.

Note: This screen appears only for Advanced installation.

12. Choose between an Internal (default) or External View server. This screen will only be shown in case of an Application Server installation. If Internal is selected, the View Server will be running inside the JBoss process. If External is selected, an additional process running the View Server will be started automatically. Note: For the External view server to work, 3 extra ports need to be open in the firewall between the web and the application server: 11099, 12500 and 14444.

Note: This screen appears only for Advanced installation.

13. Click Install in the Ready to Install the Program screen.

14.The **Esko Station Information Service** may be installed if this is the first Esko software being loaded on the machine.

If it installs, click **Continue** when it is done, or wait 10 seconds for the process to continue automatically.

15. Click Finish when the installation completes.

16.If prompted, reboot the system.



Attention: This is important; do not postpone this step!

8.4 Run the Database Schema Scripts on the Application Server

Since WebCenter 12.1, it is no longer necessary to run the database schema scripts manually. The database schema scripts can now be run from the installer dialog, for both local and remote databases.

When the database scripts are run automatically, a system console readout window will show feedback on the progress. Individual SQL statement blocks are displayed as they are being executed.

To run the database scripts automatically, database connection parameters need to be entered in the **Database Configuration** dialog which is displayed during the installation of the WebCenter Application Server:

- 1. Choose your database type from the **Database program** list.
- 2. Enter the database host name in the Database Server system field.
- 3. For SQL, enter the instance name in the Database Instance Name field.
- 4. For Oracle, enter the SID in the Database System Identifier (SID) field.
- **5.** The checkbox **Run DB update scripts during installation** determines whether the database schema scripts are run automatically during installation (preferred), or not.
- **6.** If running the scripts automatically is enabled, the **DB sysadmin connection password** field becomes available. Enter the password of the default database administrator user for your Database Server in this field.

If you still want to run the scripts manually, do the following:

- 1. Locate the ServerTools\update_db.bat file in your WebCenter installation folder (for example C:\Esko\Artios\WebCenter\ServerTools\update db.bat).
- 2. Run this file with the appropriate parameters in the console.



Tip:

Run this file without parameters first to see help about which parameters you need to use.

• If you have a SQL database, you will see this:

```
C:\Esko\Artios\WebCenter\ServerTools\update_db.bat

WebCenter Database Updater

Minimally required argument is an 'sa' password

Full usage:
update_db.bat \langle sa_password \rangle [\langle db_type \rangle [\langle db_host \rangle [\langle db_sa_use r'] ] ]

Parameters other than the password are optional. The sequence of parameters is not. If you want to specify a certain parameter, you need to specify all preceding parameters. Any of the params you do not specify, will default to the value specified at installation time. If you need to pass empty parameters, use "".

db_type can be mssqlex or mssql
mssqlex \langle default \rangle will create the webcenter DB if it doesn't exist yet

If you want to switch to oracle a reinstall is required.

Current defaults are:
\langle \langle db_type \rangle = mssqlex \langle \langle db_type \rangle = mssqlex \langle \langle db_instance \rangle = \text{VEBCENTER} \langle \langle \langle db_instance \rangle = \text{VEBCENTER} \langle \langle \langle db_user \rangle = sa

C:\Esko\Artios\WebCenter\ServerTools \rangle_=

C:\Esko\Artios\WebCenter\ServerTools \rangle_=
```

If you have an Oracle database, you will see this:

```
C:\Esko\Artios\WebCenter\ServerTools\update_db.bat

WebCenter Database Updater

Minimally required argument is a 'sysdba' password

Pull usage:
update_db.bat \( \db_{\text{password}} \) [ \( \db_{\text{bost}} \) [ \( \db_{\text{port}} \) ] \( \db_{\text{service_name}} \) [ \( \db_{\text{db_port}} \) ] \( \db_{\text{service_name}} \) [ \( \db_{\text{db_tata_table_space}} \) [ \( \db_{\text{db_tata_table_space}} \) [ \( \db_{\text{db_temp_table_space}} \) [ \( \db_{\text{db_tata_table_space}} \) ] [ \( \db_{\text{db_tata_table_space}} \) [ \( \db_{\text{db_tata_table_space}} \) [ \( \db_{\text{db_tata_table_space}} \) = \( \db_{\text{db_tata_table_space}} \) = \( \db_{\text{text{db_tatable_space}}} \) = \( \db_{\text{db_tatable_space}} \) = \( \db_{\text{text{db_tatable_space}}} \) = \( \db_{\text{text{user}}} \) [ \( \db_{\text{db_tata_table_space}} \) = \( \db_{\text{text{text{user}}}} \) [ \( \db_{\text{user}} \) ] = \( \db_{\text{user}} \) [ \( \db_{\text{user}} \) | \( \db_{\t
```

8.5 Install the Web Server

8.5.1 Uninstall IIS on the Web Server if Configured Incorrectly

In some cases IIS may already be installed on the Web Server, but configured incorrectly. For example, your hosting company may have set up IIS for you. In this case, IIS needs to be uninstalled. After which it can be installed again and configured correctly.

The procedure below describes how to uninstall IIS 7.

- 1. Start the Server Manager.
- 2. Navigate to the **Roles** section using the navigation tree.
- 3. Click Remove Roles.
- **4.** The **Remove Roles Wizard** is started, use this to remove the IIS role. Removing roles and services from the server can take a couple of minutes.
- **5.** You may get prompted to restart your server. If so please do this.

8.5.2 Install IIS on the Web Server

If IIS is not installed on your Web Server, you need to install it. The procedure below explains how to install IIS 7 on Windows Server 2008 R2, or IIS 8 on Windows Server 2012.

- 1. Open the Server Manager.
- 2. IIS 7: Click Roles in the left panel, then click Add Roles at right. IIS 8: Choose Manage > Add Roles and Features from the top menu.

This opens the Add Roles Wizard.

- 3. IIS 8: In the Select installation type screen, select Role-based or feature-based installation.
- 4. IIS 8: In the Select destination server screen, select the appropriate server (local is selected by default) and click Next.
- 5. In the Select server roles screen, select Web Server (IIS).

If the wizard prompts you to add features required for the Web Server, do so.

- 6. IIS 8: In the Select features screen, you do not need to add any additional features. Click Next.
- 7. IIS 8: Click Next in the subsequent Web Server Role (IIS) screen as well.
- 8. In the Select role services screen:
 - a) Enable ASP, ISAPI Extensions and ISAPI Filters in the Application Development section.
 If the wizard prompts you to add role services required for ASP, do so.
 - b) In **Health and Diagnostics**, enable **HTTP Logging**, **Logging Tools**, **Request Monitor** and **Tracing**.
 - c) In Management Tools, enable IIS Management Tools and IIS 6 Management Compatibility, IIS 6 Metabase Compatibility, IIS 6 Scripting Toolsand IIS 6 WMI Compatibility



- d) In Common HTTP features, make sure Default Document, Directory Browsing, HTTP Errors and Static Content are enabled.
- e) In Security, make sure Request filtering is enabled.
- 9. In the Confirm installation selections screen, check the settings and click Install.

This installs the IIS 7 or 8 Role with the settings you have selected and the default settings.

The Installation Results screen should show Installation succeeded.

10.Click **Close** to exit the wizard and restart the server if prompted.

8.5.3 Extend the Upload Limitation

IIS 7 has a limitation on how much you can upload at once (30 MB). You can change it to 2GB by following these steps:

- 1. Open IIS Manager.
- 2. Select the website for which you want enable large file uploads.
- 3. In the main window, double click Request filtering.
- **4.** Once the window is opened you may see a list of tabs (file name extensions, rules, hidden segments...).
 - Regardless of the tab you select, right-click in the main window and select Edit Feature Settings.
- **5.** Modify the **Maximum allowed content length (bytes)**: change the value to 2000000000 (a 2 and 9 zeros) to be able to upload files close to 2GB.

8.5.4 Disable 32 Bit Applications

Note: Only do this if you previously had WebCenter 10.x or 12.x installed on the same system. Previously, 32 Bit Applications needed to be enabled. Now however, this settings needs to be disabled.

- 1. In IIS, go to Application Pools and select the DefaultAppPool.
- Click Advanced Settings..., then set the Enable 32 Bit Applications option to False and click OK.
- 3. Click Recycle... at right.

8.5.5 Install the WebCenter Web Server

The Web Server components of WebCenter can be installed from a link on the WebCenter installation media.

- **1.** Log on to the Web Server as a member of the local Administrators group.
- 2. Ensure that Internet Information Services (IIS) has already been loaded by verifying that the Internet Information Services applet is in Administrative Tools in the Control Panel.

Note: If it has not been loaded, you must load it through Add/Remove Windows Components in Add/Remove Programs in the Control Panel.

- **3.** Insert the WebCenter media into the media drive, and click **Software Installation** on the menu that appears at left, then **Install WebCenter 14**.
- 4. The setup wizard opens with a Welcome screen. Click Next.
- 5. In the License Agreement screen, read the agreement, and if you agree to it, select I accept the terms in the license agreement and click Next.
- 6. In the Custom Setup screen:
 - a) Click the icon next to **WebServer**, and select **This feature**, and all subfeatures, will be installed on local hard drive.
 - b) Click the icon next to Application Server and select This feature will not be available.
 - c) If desired, click **Change** to change the installation folder.
 - d) Click Next.
- 7. In the Option Selection screen:
 - a) Enter the name of the Application Server.

This should be a different machine than the one currently running the installation.

Note: You cannot configureWebCenter with IP addresses. If the web server is not able to find the application server via name resolution, you can map the IP address of the application server and the hostname of the application server in the C:\Windows\System32\drivers\etc\hosts file. For example: 10.31.140.69 myappserver.

- Read also: https://wiki.esko.com/pages/viewpage.action?pageId=76730042.
- Configuring to use NAT translation.
- b) If you want to install WebCenter using an already-existing IIS website (rather than the **Default Web Site**), select it in the list.
- c) Click Next.
- 8. Click Install.
- **9.** The **Esko Station Information Service** may be installed if this is the first Esko software being loaded on the machine.

If it installs, click **Continue** when it is done, or wait 10 seconds for the process to continue automatically.

- 10. Click Finish when the installation completes.
- 11. Reboot the machine if prompted.

Start the WebCenter Services

After installing WebCenter, you need to start its services using the **Services** applet in the **Windows Administrative Tools**.

Start the WebCenter Services on the Application Server

1. Log on to the **Application Server** as a member of the local Administrators group.

- 2. Click Start > Settings > Control Panel > Administrative Tools > Services .
- 3. Select the WebCenter JBOSS Application Server and click Action > Start .
- 4. If not started yet, select the WebCenter Application Monitor service and click Action > Start .
- 5. Select the WebCenter CAD-X Server and click Action > Start.
- 6. If you want to change the services to start automatically when the machine reboots, do so now:
 - a) Right-click a WebCenter service and choose Properties.
 - b) In the General tab, choose Automatic in the Startup type list.
 - c) Click OK.
 - d) Repeat for each service that has to start automatically.
- 7. Close the Services tool and log off.

Start the WebCenter Services on the Web Server

- 1. Log on to the Web Server as a member of the local Administrators group.
- 2. Click Start > Settings > Control Panel > Administrative Tools > Services .
- 3. Start the Tomcat service:
 - a) Right-click Tomcat Web Server and choose Properties.
 - b) In the General tab, choose Automatic in the Startup type list.
 This makes the service start automatically when the machine reboots.
 - c) Click **OK** to close the **Properties** dialog.
 - d) Select the Tomcat Web Server and click Action > Start .
- 4. If not started yet, select the WebCenter Application Monitor service and click Action > Start .
- 5. Close the Services tool and log off.

Easily Identify when WebCenter is Ready to Access

WebCenter services load a lot of data into memory during startup of its services. It is important to watch the CPU activity before accessing a WebCenter site.

You want both the Web Server and the Application Server to have a CPU activity of under 5% before accessing the site, otherwise all components may not have started and you may experience error messages. Another way is to check whether wcr_jboss_srv.exe threads exceed 160 and wcr tomcat srv.exe threads exceed 100.

To help watch the CPU activity easily, add the CPU performance monitor to the system tray of each WebCenter server. To do this (on both the Web Server and the Application Server):

- 1. Create a new shortcut in the Start Menu > Programs > Startup folder.
- **2.** Browse to Windows\system32\TASKMGR.EXE.
- 3. Set the shortcut to Run "Minimized".

8.6 Install the On-Board Graphics Engine (OBGE) on the Application Server

The Automation Engine On-Board Graphics Engine or OBGE is required for WebCenter systems to generate view data.

8.6.1 How to perform the

Before you install the OBGE, a System Readiness Check is required. This checks whether the operating system is suited for installing and running this Esko product.

- 1. On the DVD, in the section Software installation, click the Install link in either "Standard Automation Engine Installation", "Special Automation Engine Installation" or "Installation of Automation Engine as OBGE", depending on the type of installation you want to do (as explained in Types of Installations).
- 2. In the section Installation, under Instructions, click Run the Automation Engine Readiness Check.
- 3. At the end of the Readiness Check, read the resulting messages carefully.
- **4.** If the **Readiness Check** resulted in any problem, correct it before proceeding.
- 5. Click Exit.

8.6.2 How to install the prerequisite components

Depending on the products to be installed on this particular system, various prerequisite components are required for installation. The installation wizard for the prerequisite components checks the licenses, lists the prerequisite components to install, requests confirmation for installation and then installs the required components.

The installation wizard installs the following components:

- Microsoft Visual Studio Redistributables
- Database Engine for the Automation Engine components (if you choose a Standard Automation Engine Installation)

Follow these steps:

- 1. On the DVD, in the section installation, click Install the Prerequisites Components.
- 2. Follow the instructions of the installation wizard.
- 3. When you choose a Standard installation, when asked to enter a password for the SQL Server, click Use Default to use the default sa password. Or you can enter a Password, confirm it and click Use Password to use a different password, for example because of "Strong Password" requirements.
- 4. Depending on your activated licenses, the Automation Engine Prerequisite Components First Installation process may ask you separately about the CAD-X component installation for both the Standard Edition component and the Enterprise Edition component. Click No.



5. Click Exit.

You will be redirected to the installation page to continue with the next step.

8.6.3 How to install Automation Engine 14.1

- **1.** After running the **System Readiness Check** and installing the **License Server Components**, when all prerequisites are fulfilled, you can start the installation.
- 2. Click the Install Automation Engine 14.1 link on the installation page.

 The Automation Engine 14.1 Software Installation wizard will open up.
- 3. Follow the instructions of the installation wizard.
- 4. Read the **Software and Data license agreement** carefully and select **Yes, I accept the license** agreement.
- **5.** When asked to select the products to install on this system, select **Automation Engine 14.1**. The group **Common Components** cannot be deselected and will be installed on all systems.
- 6. Select the **Destination Folder** for the chosen products or accept the defaults.
- 7. Follow the instructions of the installation wizard.
- 8. At the end of the installation, click Finish.

The pre-installation task checks the password complexity rules and domain policies. If the default password for the **BGSYSTEM** user does not fulfill the requirements, a pop-up dialog requests a password.

During installation, only a **BGSYSTEM** user is created. This user will be used as Automation Engine **System Account** (you can choose to change it later using *the System Account page*).

A clean installation ends with two empty user groups: BGUSERS and BGADMIN.

Learn more about *Users and Groups* in the separate chapter *Pre-Install IT Requirements Guide*.

9. Testing WebCenter

On the Application Server and the Web Server, ensure IIS and the WebCenter services are started and configured to start automatically.

After starting/restarting the WebCenter services, always wait a few moments until the CPU processor activity on both servers become idle (<5%) before attempting to access the login page.

Testing each facet of WebCenter in the exact order below helps to easily and quickly identify points of failure, if any.

- IIS Connectivity use IIS Manager to access the WebCenter_Inst site
- IIS Security settings can access the home page after logging in
- Database connection and Schema can add a new record to the database
- FileStore connectivity can write a file to the FileStore and then retrieve it
- View Data generation can upload a graphic file and the OBGE does its job
- View and Annotate applet can launch the applet successfully on a Graphic file

10. Configuring WebCenter

10.1 Configure the OBGE

The Pilot lets you configure the Automation Engine On-Board Graphics Engine (OBGE) for use with WebCenter.


You must create a container and a hotfolder pointing to the WebCenter FileStore.

10.1.1 Create a Container

- 1. Log on to the Application Server as a member of the local Administrators group.
- 2. Double-click the **Pilot** icon on the desktop.
- **3.** In the **Logon Information** dialog, enter admin as the **User Name** and admin as password. Type the name of the Application Server in **Server Name**. Click **OK**.

This opens the Pilot.

4. Go to **Tools** > **Containers** to open the **Containers** window.



5. In that window, go to File > New or click ...

This opens the Create Container Wizard.

- 6. In the Welcome screen, click Next.
- 7. In the Location of the Job Container screen, select Existing Shared Folder and click Next.
- **8.** In the **Location of the Network Folder** screen, type the name of the Application Server in the **Computer Name** field and click **Next**.
- 9. In the Select the shared folder screen, select the FileStore share and click Next.

10. Click Finish and close the Containers window.

10.1.2 Create a JDF Hot Folder (Access Point) for WebCenter

- 1. Choose Tools > Access Points from the Pilot main menu.
- 2. Click the Create a new Access Point button.
- 3. Choose type Folder and click OK.
- 4. Enter a Name.
- **5.** In the **Folder Settings** tab, specify the **hotin** folder. This should look like: file://myserver/FileStore/JDFHotfolder/hotin.
- **6.** In the **Monitoring** tab, set **Check every...minutes** to a low number preferably, the recommended setting is **1**.
- 7. In the Automatic Actions tab, fill in the hotout folder in the Move File to and Output Folder fields. This should look like: file://myserver/FileStore/JDFHotfolder/hotout. Make sure Action is set to Process JDF.
- 8. Click OK.

The Hot Folder/Access Point now appears in the Pilot and is ready for use.

10.1.3 Improve the Performance of View Data Generation

By default, the OBGE only polls the Hot Folder once a minute to see if there are view data requests to process. To decrease this wait to 5 seconds, do the following on the Application Server:

- 1. Log in as Admin or as a member of the Admins group on the Application Server.
- 2. Open a command prompt and change to the C:\ drive by typing C:\ and pressing Enter.
- **3.** Change directories by typing cd \esko\bg_prog_fastservcltnt_vXXX\com_win where XXX is the OBGE version you have (for Esko Software Suite 14, it is 140). Press Enter.
- 4. Type cfsedt2 and press Enter.
- **5.** Log in to the **Esko Automation Engine Configuration Tool** using admin as both the username and password. The server should be the name of the Application Server.
- 6. Expand Servers > Hot Folders > Properties.
- 7. Select hf.pollinterval in the left pane.
- **8.** In the right pane, change 60 to 5, making sure to keep the beginning and ending double quotation marks.
- 9. Click Change.

The OBGE will now poll the Hot Folder every 5 seconds instead of only once every minute.



10.2 Configuring the E-Mail Notifications

Use the E-Mail Notifications page to configure the e-mail environment for the notifications framework. Only WebCenter Administrators can access this page.

10.2.1 Configure E-Mail Notification


While logged in to the WebCenter web interface as an administrator:

- 1. Go to Admin > Configuration > E-Mail Environment Setup .
- 2. Set up your e-mail environment:

Setting	Description
E-Mail Service Protocol	WebCenter only supports the SMTP protocol.
E-Mail functionality enabled	To enable/disable e-mail functionality.
E-Mail debugging output in log	To enable/disable e-mail debugging output in log files.
E-Mail Service Host	The address for the preferred mail server that will act as the server for dispatching WebCenter e-mail notifications (this server has to comply to the selected protocol type (see above)).
E-Mail Service Port Number	The port number on which the defined mail server is listening for incoming e-mails.
Outgoing E-Mail Notifications' "FROM" Address	Supply a valid e-mail address. This will be used in the "From" e-mail header for every e-mail sent by WebCenter.
E-Mail Session Authentication	Select this option if the mail server connection requires authentication with a user name and password.
E-Mail Service Username	Provide the mail account user name if authentication is required.
E-Mail Service Password	Provide the mail account password if authentication is required.
	Note: This password is stored in an encrypted form.

3. Click Send Testing E-mail.

The **Test E-Mail Environment Settings** page appears.



4. Type a Recipient address and click Send E-mail.

WebCenter attempts to send an e-mail to the recipient.

The E-Mail Configuration page appears, displaying a message depending on the result of the test:

- Test E-Mail Sent: The environment is set up correctly.
- JMS System Error: Communication with the JBoss' proprietary messaging framework failed.
 An administrator should check the JBoss server configuration and/or log files for possible causes.
- Mail Server Connection Error: The connection to the specified mail server did not succeed.
 Either the data the administrator supplied on the e-mail environment setup page was incorrect, or the mail server is currently down.

An administrator should either check the e-mail environment settings for possible misspellings or contact the mail provider as to the status of the mail server.

Note: The settings you defined are saved in the database. For updates from older WebCenter installations, the email setup is first loaded from the old <code>emailconfig.xml</code> file and the settings are subsequently stored in the database.

10.3 Configure WebCenter for Use with ArtiosCAD Enterprise

10.3.1 Configuring BLOBs

ArtiosCAD Enterprise supports the use of BLOBs in the database. BLOBs are Binary Large OBjects - files stored as data in the database. Using BLOBs is transparent for the user.



When you configure ArtiosCAD Enterprise to use BLOBs, it also stores managed documents in the WebCenter FileStore as a cache to improve performance. If you delete a file from the FileStore, the next time you save it in ArtiosCAD Enterprise, it will be recreated in the FileStore from the BLOB.

Note:

You should decide if you want to use BLOBs when you install WebCenter. Switching to using BLOBs after having used ArtiosCAD Enterprise is not recommended or supported.

Editing appconfig.xml on the Application Server

To enable BLOBs, you must change a line in a configuration file on the Application Server. On the Application Server:

- 1. Log in as Administrator or as a user with administrative privileges.
- 2. Make a backup copy of C:\Artios\WebCenter\config\appconfig.xml. This file will be on the C: drive no matter where you installed WebCenter.
- 3. Open the file named in the previous step in a text editor such as Notepad.
- 4. Scroll down to <store files in blob value="false"/> and change false to true.
- 5. Save the file and exit the text editor.

Restarting Services

Once you have changed appconfig.xml on the Application Server, restart all the Application Server's WebCenter services to start using BLOBs in ArtiosCAD Enterprise.

- **1.** On the Application Server, still logged in as Administrator or as a member of the local Administrators group, open the Services applet in the Administrative Tools group in Control Panel.
- 2. Restart the following services by clicking each one and then clicking the Restart link:
 - a) WebCenter JBOSS Application Server
 - b) WebCenter CAD-X
- 3. Close the Services applet and log off the Application server.

ArtiosCAD Enterprise is now configured to use BLOBs. Note that WebCenter will keep copies of managed documents in its FileStore to improve performance.

10.3.2 Step 2 - Optionally Running the Board Importer Batch File

Important: The steps described in this section are only needed in case the boards are not installed automatically during the ArtiosCAD Defaults installation, which is highly recommended. If you plan to install the boards during the Defaults installation, please skip this step.

In case the boards were not installed yet, follow this procedure after logging in to WebCenter for the first time:

- **1.** Log in on the Web server as a member of the local Administrators group.
- 2. Start a Command Prompt window.
- **3.** Change directories to ..\WebCenter\WebServer\Boards.
- 4. Run the Board Import utility ImportBoards.bat which takes the following arguments.

- a) -username name of the WebCenter user doing the import, usually admin.
- b) -password password of the WebCenter user doing the import.
- c) -url URL to the WebCenter server.
- d) -dir Directory containing the migration files (same directory as the batch file).
- e) -output Specifies the optional creation of an XML file with the returned status of the procedure.

An average command would be something like this: ImportBoards -username admin - password adminpassword -url http://server/WebCenter_Inst -dir C:\Esko \Artios\WebCenter\WebServer\Boards

5. Press Enter after typing the command. The batch file will run and load the ArtiosCAD board information into WebCenter.

10.3.3 Step 3 - Loading the ArtiosCAD Defaults

The next step is to install and run the ArtiosCAD Defaults installer.

Note:

Even if you do not plan to use WebCenter in combination with ArtiosCAD Enterprise, it is still necessary to install the Default in order for WebCenter to be able to process CAD files properly. Therefore, it is highly recommended to install the Defaults, even if you do not plan to use CAD files initially.

Note:

The system you use for loading the Defaults must be able to keep the Defaults on it. You will have to follow the same process to load future Defaults and the new installation will reference the older version's Defaults as part of its installation. We recommend using the Application Server for this process.

Note:

This procedure takes a significant amount of time. We recommend starting it and doing other things until it completes.

- 1. Log in to the Application Server as a member of the local Administrators group.
- 2. Insert the ArtiosCAD Enterprise media into the drive.

The ArtiosCAD Enterprise installer should appear. If it does not, run setup.exe in the root directory of the media.

- 3. Click Install ArtiosCAD Defaults.
 - a) Choose the language in which the setup program will run and click **OK**.
 - b) Click **Next** in the **Welcome** dialog box.
 - c) Click I accept the terms in the license agreement and click Next.
 - d) In the **Defaults Language Choice** dialog box, select the language of the Defaults to upload to WebCenter and click **Next**. Only one language may be uploaded per session, so to install more than one language, repeat this procedure.
 - e) Enter your WebCenter server URL, admin username, and admin password in the **WebCenter Server Information** dialog box and click **Next**.

- f) In the Boards dialog, you can choose to **Import Boards** automatically. This is highly recommended.
- g) In the Defaults Source dialog box, you can choose a version of ArtiosCAD from which to merge Shared Defaults into Enterprise. To use the delivered Shared Defaults, choose Use this version's defaults; otherwise, choose Merge defaults from an earlier version, and select either Standard ArtiosCAD Version or Enterprise ArtiosCAD Version. If you choose Enterprise, set Copy Location Defaults from previous version and Copy User Defaults from previous version if desired. Click Next.
- h) If you chose to migrate defaults in the previous step, in the Update Version Selection dialog box, select the version of ArtiosCAD whose defaults you want to migrate into the version you are installing.
- i) Click Install to begin the installation.

A progress indicator will appear.

- 4. If you chose to copy Location and User Defaults from a previous version, in the Copy Projects dialog box, select those Defaults Projects to copy into the version you are installing. All Defaults Projects are selected by default, but you may select and deselect them as desired. Check Overwrite if exists if there is a chance the Project(s) may already exist. Click OK in the dialog boxes that appear after the copying is complete. This process may take a significant amount of time depending on the number of Projects you select.
- 5. Click Finish when the installation process is done.

10.3.4 Configuration in the WebCenter User Interface

Note: See the WebCenter Administration Guide for more details about the following steps.

- 1. Log on to WebCenter with the admin account (see Log On to WebCenter and Change the Admin Password).
- 2. Configure a Company and Location for the initial ArtiosCAD Enterprise users.
- **3.** Create a custom group, if desired, for the initial ArtiosCAD Enterprise users.
- **4.** Create the initial ArtiosCAD Enterprise users. While creating them:
 - a) Make sure they are at least Project Managers with Limited Visibility of Companies and Groups.
 - b) Assign them to the **Company** and **Location** you created.
 - c) Assign them to one or more groups.
 Even if you did not create any custom group, you should assign them to the USERS group.
- 5. Invite them to the System Defaults Project (which is Shared Defaults in ArtiosCAD Enterprise).

Tip: You can do this either individually for every user or once through Group membership if you added all users to the same group (such as **USERS**).

Inviting them to the Project means that they will be able to use the Defaults.

In order for users to change Shared Defaults, they must have Full permissions on the Project and be members of the **ADMINS** group.

Note: All ArtiosCAD Enterprise users must be invited to the **System Defaults** Project. Users who are not invited to the project will receive a UFANEX error when they launch ArtiosCAD Enterprise.

10.4 Secure your WebCenter Site with SSL

SSL is a **protocol for securing communication over the Internet**. It works by using a private key to encrypt data that is transferred over an SSL connection.

URLs using an SSL connection start with https://instead of http://.

To use SSL, you are required to obtain an **SSL certificate** and install it into Internet Information Services (IIS) on the Web Server.

Note: We strongly recommend you secure your WebCenter site with SSL, especially if you plan to use WebCenter over the internet (not only within a Local Area Network).

10.4.1 Secure the WebCenter Web Server with SSL

You will need to:

- 1. Create a Certificate Signing Request (CSR) on page 43.
- 2. Request an SSL Certificate from a Certificate Authority on page 44.
- 3. Install the Intermediate SSL Certificate on page 45.
- 4. Install your Signed Certificate on page 46.
- Export your Certificate if Necessary on page 46.
 You only need to do this if you haven't installed the certificates directly on your Web Server.
- 6. Bind your Certificate to your WebCenter Site on page 47.
- 7. Redirect HTTP Traffic to HTTPS on page 47.

Create a Certificate Signing Request (CSR)

To get an SSL certificate, you need to first create a Certificate Signing Request, that you will send to a Certificate Authority.

- 1. On the Web Server, click **Start**, then **Administrative Tools**, then **Internet Information Services** (IIS) **Manager**.
- 2. In the Internet Information Services (IIS) Manager dialog, click your server name (at left).
- 3. In the dialog's central pane, double-click the Server Certificates icon in the Security section.
- 4. In the Actions pane at right, click Create Certificate Request...

This opens the **Request Certificate** wizard.

- 5. In the Distinguished Name Properties screen, enter your information as follows:
 - **Common Name**: the name through which the certificate will be accessed (usually the fully-qualified domain name, for example www.domain.com).



- Organization: the legally registered name of your organization/company.
- Organizational unit: the name of your department within the organization.
- City/locality: the city in which your organization is located.
- **State/province**: the state in which your organization is located.
- Country/region: the two-lettered ISO-3166 country code of the country in which your
 organization is located. You can find a list of valid country codes on http://www.ssl.com/csrs/country_codes.

Click Next.

- 6. In the Cryptographic Service Provider Properties screen:
 - leave Cryptographic Service Provider to Microsoft RSA SChannel Cryptographic Provider.
 - in Bit length, select 2048 or higher.

Click Next.

7. In the **File Name** screen, enter a name for your Certificate Signing Request, and select a location in which to save it.

Click Finish.

Request an SSL Certificate from a Certificate Authority

The customer is responsible for choosing the SSL provider (Certificate Authority), obtaining certificates, as well as following that company's specific instructions for installation and configuration.

Esko cannot obtain SSL certificates on behalf of its customers.

1. Send your Certificate Signing Request file to a public Certificate Authority.

Note:

- If you do an Internet Search for "SSL certificate", you will find many providers with different pricing and options. We have good experiences with VeriSign, Network Solutions, Godaddy.com, and Thawte.
- The application process can take up to 30 days... Start the application process well in advance!
- If your company has a DNB (Dun & Bradstreet) number, the application process will be a lot easier and quicker if you can provide it.
- Your certificate will be linked to your website (for example webcenter.domain.com).
 Changing your website name will require a new certificate.
- 2. The Certificate Authority will provide you with:

 an intermediate certificate, verified by the root certificate installed by default on your Web Server (where you created the Certificate Signing Request),

Note: You may need to download this from a web link.

 your server certificate, verified by that intermediate certificate (signed by the Certificate Authority).

Make sure you have both certificates before going further! You will need to install both of them on your Web Server.

3. Copy those certificates to your Web Server.

Install the Intermediate SSI Certificate

You need to install the intermediate certificate before you install your signed certificate.

- 1. On your Web Server, click Start, then Run...
- 2. Type mmc and press Enter.
- 3. In the Microsoft Management Console (Console1) window that opens, go to File > Add/Remove Snap-in...
- 4. In the Add or Remove Snap-ins dialog, select Certificates, and click Add.
- 5. In the Certificates snap-in dialog, select Computer Account, and click Next.
- 6. In the Select Computer screen, select Local Computer, then click Finish.
- 7. Click OK in the Add or Remove Snap-ins dialog.
- 8. In the Console1 window:
 - a) expand the Certificates (Local Computer) folder,
 - b) right-click Intermediate Certification Authorities, and go to All Tasks > Import...
- 9. In the Certificate Import Wizard dialog:
 - a) click Next to get to the File to Import screen,
 - b) browse to the location containing your intermediate certificate file,
 - c) in the Open dialog, change the file extension filter to PKCS #7 Certificates (*.spc;*.p7b),
 - d) select your * iis intermediates.p7b file, and click Open.

Note: Only install your intermediate certificate, not your signed certificate in this area! Installing your signed certificate here would remove your intermediate certificate from the list, and you would need to reinstall it.

e) Click Next.

10.In the Certificate Store screen:

- a) select Place all certificates in the following store,
- click Browse, select Intermediate Certification Authorities in the Select Certificate Store pop-up, and click OK,
- c) click Next.

11.Click:

- a) Finish in the Certificate Import Wizard dialog,
- b) **OK** in the **Certificate Import Wizard** pop-up stating that the import was successful.



12. Close the Console1 window, then click No in the pop-up asking to save the console settings.

Install your Signed Certificate

Once your intermediate certificate is installed, install your signed certificate:

- 1. On the Web Server, extract your *.cer certificate file from the zip file you got from the Certificate Authority.
- 2. Click Start, then Administrative Tools, then Internet Information Services (IIS) Manager.
- 3. In the Internet Information Services (IIS) Manager dialog, click your server name (at left).
- 4. In the dialog's central pane, double-click the Server Certificates icon in the Security section.
- 5. In the Actions pane at right, click Complete Certificate Request...

This opens the Complete Certificate Request wizard.

- 6. In the Specify Certificate Authority Response screen:
 - a) browse to your *.cer certificate file,
 - b) enter a Friendly name for your certificate.This will be used by the server administrator to easily distinguish the certificate.
 - c) Click OK.

Your certificate is now installed. If you cannot see it yet in the **Server Certificates** list of the **Internet Information Services (IIS) Manager** dialog, press **F5** to refresh.

Export your Certificate if Necessary

We recommend you create the *Certificate Signing Request* and install the certificates directly on your WebCenter Web Server.

However, if you do this on another server, you can export the signed certificate then import it on your Web Server.

- 1. If you haven't done so already, install the intermediate certificate on your Web Server.
- **2.** Export your signed certificate from the server it is installed on:
 - a) In Internet Information Services (IIS) Manager, select your certificate in the Server Certificates list and click Export... in the Actions pane at right.
 - b) In the **Export Certificate** dialog that opens:
 - **1.** Type a file name in **Export to**, or click the browse button to navigate to a file in which to store the certificate for exporting.
 - 2. Type a Password if you want to associate a password with the exported certificate.
 - 3. Retype the password in **Confirm password** and click **OK**.

This exports your certificate to a .pfx file.

- **3.** Import your signed certificate on your Web Server:
 - a) Click Start, then Administrative Tools, then Internet Information Services (IIS) Manager.
 - b) In the Internet Information Services (IIS) Manager dialog, click your server name (at left).
 - c) In the dialog's central pane, double-click the Server Certificates icon in the Security section.
 - d) In the Actions pane at right, click Import...
 - e) In the Import Certificate dialog that opens:
 - 1. browse to your Certificate file (.pfx),

- 2. enter the Password associated with your certificate if there is one,
- 3. make sure that Allow this certificate to be exported is selected.

Note: This is important, as due to a bug in IIS, the *site binding* will not work if the certificate is not exportable.


4. Click OK.

Your certificate is now installed on your Web Server. If you cannot see it yet in the **Server Certificates** list of the **Internet Information Services (IIS) Manager** dialog, press <u>F5</u> to refresh.

Bind your Certificate to your WebCenter Site

Once you have installed your certificate on your Web Server, you need to bind it to your WebCenter site, so that the certificate will be used to authenticate your WebCenter site when users browse to it.

- Still in the Internet Information Services (IIS) Manager, right-click the Default Web Site node in the Connections pane, (or the node of the IIS website you have deployed your Web Server on if it's not the default website) and select Edit Bindings...
- 2. In the Site Bindings dialog that opens, click Add.
- 3. In the Add Site Binding pop-up:
 - a) Choose https as Type.
 - b) Leave the default https Port (443).
 - c) In the SSL Certificate list, select your Web Server.
 - d) Click **OK** and then **OK** again.



Redirect HTTP Traffic to HTTPS

To ensure security, end users should only use https:// to access your WebCenter site. If someone accidentally uses http:// instead, they will not be using a secure connection.

To avoid this, you can make sure http:// traffic to your WebCenter site is automatically redirected to https://. This will be transparent for the users (they will not get an error page but will simply be able to access your site through https://).

For this, you need to download a (free) extension for IIS.

1. On your Web Server, download and install the URL Rewrite extension for IIS.



Go to http://www.iis.net/downloads/microsoft/url-rewrite, click the **Install this extension** button and follow the steps on screen.

- 2. In the Internet Information Services (IIS) Manager, make sure SSL is not required so users don't get an error when connecting to your site using http://:
 - a) Select the **Default Web Site** node in the **Connections** pane, (or the node of the IIS website you have deployed your Web Server on if it's not the default website).
 - b) Double-click **SSL Settings** in the center pane.
 - c) Under SSL Settings, make sure that Require SSL is not selected.
- 3. Click **Default Web Site** or the node of your IIS website again, then double-click **URL Rewrite** in the center pane.
- 4. Create a blank inbound rule:
 - a) Click Add Rule(s)... in the Actions pane at right.
 - b) In the Add Rule(s) pop-up, click Blank rule under Inbound rules, then click OK.

The center pane now shows the **Edit Inbound Rule** form.

- **5.** Edit the rule as follows to perform the automatic redirection:
 - a) Enter a Name for the rule, for example HTTP to HTTPS redirect.
 - b) Under Match URL, fill in the settings as follows:

Requested URL	Matches the Pattern
Using	Regular Expressions
Pattern	(.*)
Ignore case	on

- c) Under Conditions, select Match All in Logical grouping.
- d) Add the first condition:
 - 1. Click the Add... button to open the Add Condition pop-up.
 - 2. Fill in the settings as follows:

Condition input	{HTTPS}
Check if input string	Matches the Pattern
Pattern	off
Ignore case	on

This ignores addresses starting with https:// (they don't need to be redirected).

- 3. Click OK.
- e) Add the second condition:
 - 1. Click the Add... button to open the Add Condition pop-up.
 - 2. Fill in the settings as follows:

Condition input	{SERVER_ADDR}
Check if input string	Does Not Match the Pattern

Pattern	::1
Ignore case	on

This ignores addresses using localhost through IPV6 (::1), as forcing https://forthose would give a certificate error as the one below (because the certificate is linked to your site name and not the server's IPV6 address).



There is a problem with this website's security certificate.

The security certificate presented by this website was issued for a different website's address.

Security certificate problems may indicate an attempt to fool you or intercept any data you send to the server.

We recommend that you close this webpage and do not continue to this website.

- Click here to close this webpage.
- Continue to this website (not recommended).
- More information
 More informat
- 3. Click OK.
- f) Add the third condition:
 - 1. Click the Add... button to open the Add Condition pop-up.
 - 2. Fill in the settings as follows:

Condition input	{SERVER_ADDR}
Check if input string	Does Not Match the Pattern
Pattern	127.0.0.1
Ignore case	on

This ignores addresses using localhost through IPV4 (127.0.0.1), as forcing https://for those would give a certificate error (because the certificate is linked to your site name and not the server's IPV4 address).

- 3. Click OK.
- g) Under **Action**, fill in the settings as follows:


Action type	Redirect
Redirect URL	https://website-name.com/ {R:1}
	where website-name.com is the name of your WebCenter site, to which you have linked your certificate

49



Append query string	on
Redirect type	Found (302)

Your rule should look like this:



h) Click **Apply** in the **Actions** pane at right.

You should now see your rule in the **URL Rewrite** list in the center pane.

6. Browse to your WebCenter site using http:// and check that it is redirected to a https://connection.

10.4.2 Install SSL Certificates on the Workflow Production Server

If...

- you are planning to integrate your Automation Engine server with WebCenter,
- your WebCenter site is secure (it demands https://connections),
- your Automation Engine server and your WebCenter are not located within the same Local Area Network,

... you need to make sure your Automation Engine server can communicate with your WebCenter server over https://.

Important:

If you have installed your certificates properly on the Web Server (the *intermediate certificate* and the *signed server certificate*), **this should work without you having to do anything**.

If you haven't, or you are still experiencing connection problems, you should import the WebCenter certificates into the Automation Engine keystore.


This can also apply when WebCenter and Automation Engine are in the same LAN, if https://communication is also enforced inside the LAN. Check with your network administrator if this is the case.

Export the Certificates from the WebCenter Site

- 1. Log on to the Automation Engine server as a local administrator.
- 2. Open a web browser and navigate to the secured WebCenter site.
- 3. Examine the WebCenter site's certificates.


How you do this depends on the web browser you use; for example in Internet Explorer:

a) Click the lock icon at the end of the address bar and click View certificates in the pop-up.




b) In the Certificate dialog, click the Certification Path tab.


This tab displays the certificate hierarchy. Each top-level entry in the hierarchy represents a certificate.



- 4. Export all the certificates (top-level entries) in the hierarchy:
 - a) Highlight the first certificate in the hierarchy (for example, Thawte Server CA (SHA1)).
 - b) Click View Certificate.
 - c) Click the **Details** tab.



- d) Click Copy to File to begin the Export Wizard. Click Next.
- e) Select DER encoded binary... (.CER) and click Next.



- f) Click **Browse** or type in a valid path and name the certificate (*.cer). We recommend using a short path and name (such as c:\temp\vali.cer). Click **Next**.
- g) Click Finish, then OK and once more OK.



h) Repeat these steps until you have exported all the certificates. Close the web browser when you are finished.

Import the Certificates into the Workflow Server Keystore

While still logged on to the Automation Engine server as a local administrator, import the certificate files into the Automation Engine keystore:

- 1. Open a DOS command prompt.
- 2. Change to the Esko Automation Engine software directory which contains the keytool utility: \bg_prog_fastserver_vxxx\jre\bin

For Suite 14, this will typically be c:\esko\bg prog fastserver v140\jre\bin

3. Run the import utility for each certificate downloaded, in the proper order: keytool -import -file <path>*.cer -alias <aliasname> -keystore <keystore path>.

Your <keystore_path> is the path to bg_prog_fastserver_vxxx\jre\lib\security \cacerts. For example: c:\esko\bg_prog_fastserver_v140\jre\lib\security \cacerts.

You will be prompted for a password. The password is: changeit (case sensitive).

4. You might be asked to trust the certificate. Enter Y for Yes.

It is also possible that the tool tells you that this certificate is already installed. If so, that's ok, go on with the next certificate.

You should get a successful message like Certificate was added to keystore.

- 5. Repeat for each certificate to import in the hierarchy.
- 6. Reboot the Automation Engine computer to ensure that the changes take effect.

Example

You are running Automation Engine 14 and the Automation Engine server software is installed on E:\Esko.

You have downloaded two certificates from the WebCenter site in the folder c:\temp: valicert.cer and starfield.cer.

valicert.cer was first in the hierarchy, so you would import this first, then repeat for starfield.cer.

You would proceed as follows:

- 1. Using a command prompt, go to e:\esko\bg prog fastserver v140\jre\bin.
- 2. Type Keytool -import -file c:\temp\valicert.cer -alias valicert keystore e:\esko\bg_prog_fastserver_v140\jre\lib\security\cacerts
- 3. If asked for the password, type changeit.
- 4. If asked to trust the certificate, type Y.
- **5.** Repeat the same command for the next certificate, startfield.cer.
- 6. Reboot the Automation Engine computer to ensure that the changes take effect.

Import the Certificates into the Workflow Client Keystore

With a secured WebCenter site (requiring https://), you cannot check the connection between Automation Engine and WebCenter with the **Check Connection** button in **Configure**.

To be able to do this, you need to install the Web Server certificates in the Automation Engine **client** keystore too (even if the client is running on the same machine as the Automation Engine server).

Tip:

You should also do this if publishing fails because Automation Engine doesn't have the appropriate certificates. Typically, this gives an error message like the one below:

```
javax.net.ssl.SSLHandshakeException:
   sun.security.validator.ValidatorException: PKIX path building failed:
    sun.security.provider.certpath.SunCertPathBuilderException: unable to
   find valid certification path to requested target
```

- 1. While logged on to the Automation Engine client machine as a local administrator, open a DOS command prompt.
- 2. Change to the Esko Automation Engine software directory which contains the keytool utility: \bg prog fastservercltnt vxxx\jre\bin

For Suite 12, this will typically be c:\esko\bg prog fastservercltnt v120\jre\bin

Note: For the client, make sure to use <code>bg_prog_fastservercltnt</code> and not <code>bg_prog_fastserver</code> as for the server!

3. Run the import utility for each certificate downloaded, in the proper order: keytool -import -file <path>*.cer -alias <aliasname> -keystore <keystore_path>.

Your <keystore_path> is the path to bg_prog_fastservercltnt_vxxx\jre\lib\security\cacerts. For example: c:\esko\bg_prog_fastservercltnt_v120\jre\lib\security\cacerts.

You will be prompted for a password. The password is: changeit (case sensitive).

4. You might be asked to trust the certificate. Enter Y for Yes.

It is also possible that the tool tells you that this certificate is already installed. If so, that's ok, go on with the next certificate.

You should get a successful message like Certificate was added to keystore.

- 5. Repeat for each certificate to import in the hierarchy.
- 6. Reboot the Automation Engine computer to ensure that the changes take effect.

10.5 Install Certificates for LDAPS on the Application Server

To connect your WebCenter installation to a secure LDAP server (LDAPS), you have to install a certificate obtained from that LDAPS server.

- 1. Open a command prompt on the WebCenter Application Server.
- **2.** Change directory to the location of \WebCenter\ApplicationServer\LDAP \CertInstall.bat.
- **3.** Issue the following command: CertInstall servername:port, where servername is the name or IP of the LDAP server and port is the port used for secure connection (typically 636).

If successful, a list of certificates sent by the server is displayed (ignore any additional messages).

```
Server sent 1 certificate(s):

1 Subject CN=webcenter2.esko.com
Issuer CN=webcenter2.esko.com
sha1 25 59 4e e9 9d 33 3e 15 ea 03 8f 6e 03 6a fa c9 29 eb 79 70
md5 5a 0f 6a 08 c1 0d 61 3d bc e2 9f 73 58 45 39 f6

Enter certificate to add to trusted keystore or 'q' to quit: [1]
```

4. To install a given certificate, enter its number in the list and press Enter.

We suggest that you install all certificates. Only one certificate can be installed each time you run CertInstall so it can be necessary to run it multiple times.

Note:

Troubleshooting the certificate installation

The certificates should be properly installed. If not, try these troubleshooting tips:

Server or port name is not correct

If the supplied parameters are wrong, the result can look something like the following:

In this case, contact your IT system administrator and verify the parameters supplied.



10.6 Integrate WebCenter with a Workflow Production Server

You can configure WebCenter to integrate with your existing Automation Engine production server. In this documentation, we assume that you have both these applications installed and running properly.

10.6.1 Understanding WebCenter Integration

WebCenter can run without Automation Engine, but its full potential is realized when integrating both systems.


Integrating WebCenter with an Automation Engine production server allows you to upload production files to WebCenter for approval and advanced project management.

To make this collaboration between the systems possible, you must:

- Add the WebCenter site information in the Automation Engine Configure window.
- Configure the Job Web Page URLs in the Automation Engine Configure window.
- Set up the WebCenter View information for the Automation Engine users.
- Set up the Publish on WebCenter ticket.

Add the WebCenter Site Information

- **1.** Launch the Automation Engine Pilot and connect to the production server with an administrator account.
- 2. Choose Tools > Configure .
- 3. In the Configure window, select WebCenter Sites in the left pane.
- 4. Click the + icon.



5. In the Website field of the Delivery area, enter the URL of the WebCenter site (for example: http://wcrserver/WebCenter_Inst).

Note: If your site uses secure HTTP, make sure to enter an HTTPS address.

- **6.** Click **Open...** to test the connection. The login page for WebCenter should appear. If it doesn't, check your settings.
- 7. If the Automation Engine server and the WebCenter Application Server are not on the same LAN, deselect **WebCenter and Automation Engine are in the same LAN**.

The **User Name** and **Password** fields then become available. This is where the Automation Engine Approval Client configuration in WebCenter is used.

Create a user name and password combination in WebCenter, then enter that same (case-sensitive) user name and password in the appropriate fields in Automation Engine **Configure**.

Click Check Connection to test the connection.

Important: You must be using the Pilot on the Automation Engine server itself to run this check.

A dialog box appears, proving that the connection works and displaying the WebCenter version number.

- 8. If the Connect to JDF Processor area is visible, leave JMF selected in it.
- 9. Click Check to test the connection.

An **Info** dialog appears, reporting that the connection is OK. Click **OK**.

If this dialog does not appear, check your settings.

- 10.On the left of the Configure window, scroll down and select the new WebCenter1 entry under WebCenter Sites.
- **11.**Click **File** > **Rename** and enter a descriptive name for your WebCenter site.
- 12.Click File > Save to save the settings.

Configure the Job Web Page URLs

The Job Web Page enables you to go to your WebCenter project from within your Automation Engine Job.

- **1.** Launch the Automation Engine Pilot and connect to the production server with an administrator account.
- 2. Choose Tools > Configure.
- 3. In the Configure window, select Jobs > Job Web Page in the left pane.
- **4.** In the Address field, enter the URL of the WebCenter site (for example: http://pacwebserver/WebCenter).
- 5. Still in the Address field, append this text to the end of the URL: /projdetails.jsp? projectName=



Attention: This is case-sensitive; enter it exactly as written. Do not include a space or period at the end.

- 6. Click +[] InsertSmartNames.
- 7. In the SmartNames column, scroll down and click JobName.
- 8. Click Insert to append it to the URL in the Address field.
- 9. Click Close to return to the Configure window.



The result should resemble http://pacwebserver/WebCenter/projdetails.jsp?projectName=[JobName] with [JobName] in green.

10.Click File > Save to save the settings.

You can now right-click your Job folder in the Automation Engine Pilot and select **Go to Job Web Page**; this opens the WebCenter project associated with your Job in a browser.

Set Up the Publish on WebCenter Ticket

The **Publish on WebCenter** ticket in Automation Engine creates output and uploads the resulting files to WebCenter.

For more details, please see the Automation Engine documentation.

- 1. Launch the Automation Engine Pilot and connect to the production server with an administrator account.
- 2. Click the Tickets view.
- 3. Locate the Publish on WebCenter default ticket, right-click it and click Duplicate....
- **4.** In the **Save As** pop-up that opens, replace the word <code>Default</code> in the **Save As** field with a meaningful name (for example the name of your WebCenter site).
- 5. In the Scope area, select the Global option.

If you have no blue job folders containing files, you are not prompted to select the scope.

- 6. Click Save. The new ticket should appear in the list.
- 7. Double-click your new Publish on WebCenter ticket to change its settings.
- 8. On the **Destination** tab, define where you want to publish your file:
 - a) In the **Site** list, select your desired WebCenter site.
 - b) In the **Project** field, enter the **JobName** SmartName so that the files are published to the WebCenter project corresponding to your Automation Engine job.

Note:

- The project does not have to exist in WebCenter at upload time. If the project does not exist, it will be created. In this case, the person that does the upload from Automation Engine needs to be **Project Manager** in WebCenter! Otherwise the upload will fail.
- If your main goal is not to upload files but to create WebCenter Projects through Automation Engine, we recommend you use the Create or Modify WebCenter Project ticket instead (see the Automation Engine documentation for more information).
- c) Leave the Folder and Project Template fields blank unless you know the exact names of the folder and project template you want to use for every new Project.
 - In this case, enter them as appropriate; all new WebCenter Projects created with this ticket will use these values.

Note:

- The **Project Template** field refers to a template in WebCenter, not Automation Engine.
- You can only use templates that are visible by the WebCenter user performing the upload (see sub-step f).
- d) Enter a **Document Name** if you want your published document to have a name different from the input file name.

Note: If the document already exists, the task will create a new version of that document. If it exists but is in a different folder, the task will fail.

- e) Enter a **Document Description** if desired; this description will be available in WebCenter as a **Version Comment**.
- f) Leave the User Name and Password fields blank unless there is a specific (and valid!) WebCenter user who will own each document revision published using this ticket; in that case, enter the appropriate information.

If you leave these fields blank, anyone using the ticket will have to supply a valid user name and password each time it is used.

- 9. On the Publish tab:
 - a) Leave Prepare for viewing and annotating and Make available for download selected.
 - b) In the **Allow Downloading in WebCenter** area, choose the kind of files to upload to WebCenter.
 - Input files are the original files themselves.
 - PDF files for proofing are proxy files created by using the selected ticket. If you choose
 PDF files for proofing, leave the default Create SoftProof for WebCenter ticket selected,
 or choose another ticket if desired. Proxy files uploaded in this manner will have Download
 PDF for printing as an option in WebCenter.

The combination of preparing for viewing but not making available for download is intended for Graphics files that only need Approval.

- 10. On the Approval tab, deselect Start the Approval Cycle.
- 11. Click Save. Then click Yes to confirm overwriting the ticket.

10.7 Expose WebCenter to the Internet

Exposing WebCenter to the Internet is the responsibility of your local IT department. Esko cannot do this for you.

10.7.1 Register a Domain Name

Register and pay for a domain name, such as www.esko.com, to allow internet users to navigate to your WebCenter site.

Once you have registered the domain name, your company is the only one authorized to use that specific domain name for a certain period.

Contact a proper authority (VeriSign, GoDaddy, etc) and purchase a domain name.

10.7.2 Contact Your ISP to Set Up an A Record

The purpose of an **A record** is to associate your domain name to your public firewall/router, so web traffic (HTTP and HTTPS) going to the domain name is routed to that public firewall/router.

Think of this as telling the Postman how to get to your mailbox.

Note: It takes several days for the A record information to propagate around the world.

1. Identify the public IP Address of your router/firewall.

This is the hardware appliance your Internet connection is plugged into (i.e. T1, DSL).

For example: My T1 is plugged into a firewall with 66.55.44.33 as public IP address.

- 2. Contact your ISP and ask them to add an 'A' Record (Address record) to the global DNS (Domain Name Servers), associating your domain name and your router/firewall public IP address.
- 3. Verify that you can ping your domain name from computers inside and outside your LAN.
- 4. Ensure the reply you get contains the correct IP address for your public firewall/router.

Example

MCI is your ISP. You contact MCI and ask them to add an A record for your new domain name, www.esko.com, to forward HTTP and HTTPS traffic to your public firewall IP address of 66.55.44.33.

After about 3 days or so, this record has been propagated across the world. If someone in Thailand 'pings' the domain name www.esko.com, he/she should receive a reply with the IP address of 66.55.44.33.

10.7.3 Move the Web Server Inside the Demilitarized Zone (DMZ)

You should physically arrange the network devices so that the Web Server is in a proper DMZ architecture (between two firewalls or plugged into a DMZ port of the public router/firewall).

- 1. Configure Firewall 1 (public router/firewall):
 - a) Allowed to route traffic to Web Server inside DMZ for HTTP and HTTPS.
 - b) Default ports 80 (HTTP) and 443 (HTTPS).
- 2. Configure Firewall 2 (gatekeeper for private network):
 - a) Allowed to route traffic on specific ports to WebCenter's Application Server.
 - b) Default ports 1099, 2500, 4444.

Note: You can change the default port numbers used at any time—to do this, modify the IIS settings and the WebCenter configuration files on both the Web Server and the Application Server to reflect these custom port numbers.

10.7.4 Configure IIS to Receive Traffic

Web traffic is delivered to the public firewall because of the A record. That firewall then forwards the web traffic to the Web Server inside the DMZ.

The Web Server application (IIS) needs to be configured to pick up this traffic for processing. To do this, the Web Server must be assigned a static Private IP Address.

- 1. On the Web Server, click Start > Run and type inetmgr. Then click OK to start Internet Information Services (IIS) Manager.
- 2. Expand the Web Site node.
- 3. Right-click the Web Site node and choose Properties.
- **4.** Click the Web Site tab and verify that the **IP Address** is correct (or use the drop down list to change it).
- **5.** In the **TCP Port** field, ensure you are using the correct port for HTTP traffic; the default port is 80 (this needs to match your firewall rules).
- 6. Close IIS Manager.

11. Deploying WebCenter

WebCenter uses a three-tier installation framework to facilitate in-house development and configuration before deploying it in production form. The three tiers are the **Installation** version, the **Development** version, and the **Production** version.

Deployment Workflow


The intended workflow is to install WebCenter, deploy it to Development, modify the Development version, and then when you are satisfied, deploy the Development version to Production.

As time goes by, you can keep modifying the Development version as desired without affecting the Production version. When you are satisfied with the changes made to the Development version, you can deploy it to Production.

At the time of deployment, the custom directory is not overwritten if it already exists in a target instance, so <code>customizationConfig.xml</code> and any other customized files in the custom directory are not changed. But when a new instance is created by deployment, the custom directory is created with its default configuration.

The WebCenter Deployment Manager

The **WebCenter Deployment Manager**, located in **Start > Programs > WebCenter**, manages the deployment process. If there is more than one website on the Web Server, choose the website with which the **WebCenter Deployment Manager** will work and click **OK**.



To further develop the installed version, use the WebCenter Deployment Manager:

If you want to change the name of the development version, click the ... button in the Development
area, and specify the new name of the development version. When you have changed the name,
click **Deploy Development**.

Web authors can then modify the site at http://WebServer_name/WebCenter_Dev (or whatever name you chose earlier), while normal users can still work using the site at http://WebServer_name/WebCenter_Inst.

 Once the developed version is ready for production use, use the WebCenter Deployment Manager again.

If you want to change the name and location of the production version, click the ... button in the Production area and enter the new name. Then, click **Deploy Production**.

The site in WebCenter_Dev will be copied to WebCenter. Production use starts by users pointing their browsers to $http://WebServer_name/WebCenter$.

Note:

You can have multiple development and deployment versions of WebCenter by changing the names for each deployment, e.g. DEV1, DEV_Other, WebCenter_Prod1, and so forth.

Also, the deployment name is not case sensitive, so for example WebCenter_Dev and WebCenter_dev are considered to be the same deployment instances.

12. Localizing WebCenter

Localization is the process of making a program ready to run anywhere in the world.

It encompasses modifying the display language, the way units are displayed, decimal separators, time and date formats, and currency format to match the local user preferences.

12.1 Understanding Localization in WebCenter

WebCenter uses references to separate language files (text strings files) instead of using hard-coded words. WebCenter ships with a variety of language files. Additionally, the text strings files can be translated into any language.

Each WebCenter user can change to a different language in My WebCenter > My Preferences .

The default language can be changed in **General Preferences** at any time by any WebCenter user who is a member of the Admins group.

12.2 How to Install Custom Translations

The language files are in the languages subdirectory of the WebCenter installation on the Web Server, such as \Artios\WebCenter\WebServer\tomcat\webapps\<site name>\languages.

They are named wcstrings_xx.xml where xx is a two-letter code for the language, for example en for English, fr for French, and de for German.

1. Copy one of the existing language files, and rename the copy changing the two-letter language code to the new language code.

Note: The language code must match the official list of two-letter ISO 639-1 codes at http://www.loc.gov/standards/iso639-2/englangn.html. For example, a Danish language word strings file would be named wcstrings da.xml.

- 2. Translate the strings in the file.
- **3.** On the Web Server, open \Artios\WebCenter\WebServer\tomcat\webapps \WebCenter_instance\config\config.xml in a text editor or an XML editor. In the Languages section of the file, add a key for the new language, for example <Language key="da"/> for a Danish translation.
- 4. Put the translated language file in the languages subdirectory of the WebCenter installation.
- **5.** Open every other wcstrings_xx.xml file and add a <NLanguage_xx>Language</NLanguage_xx> string after the strings for the existing languages.

For example, add the string <NLanguage_da>Danish</NLanguage_da> to install a Danish strings file, substituting the word for Danish in the appropriate language for the string file.

- **6.** If the chosen language is a multi-byte language (such as Japanese, Chinese, or Thai), log on to the Application Server and edit \Artios\WebCenter\config\appconfig.xml. Change the value in the index_lang field to the appropriate language code that is listed in the comment below the field, and save the file.
- 7. Restart the Web Server to see the changes.

13. The Help System

Old style dynamic help system

WebCenter uses a dynamic help system that checks for the existence of specifically-named XSL files on the Web Server in \Artios\WebCenter\WebServer\tomcat\webapps\<\WebCenter instance>\help.

A Help link will appear in the menu of the page that has the same name as an XSL file in this directory. The content of a Help file can be anything provided it is in XSL and the file has an .XSL extension.

Note: Esko recommends the use of xmlspy[®] for authoring WebCenter Help XSL files. It is available from http://www.xmlspy.com. There are also shareware and freeware XSL editors available. You could also modify the sample provided using a text editor such as Notepad; do not use WordPad as it inserts its own formatting codes.

- To change the Webmaster contact name and e-mail address displayed on the login help page, edit login.xsl.
- If using foreign-language files, append _xx (where xx is the code for the language) to the end of the file name before the extension, such as login_fr.xsl for a French help file for the login page.

When determining if a Help link should be on a page, WebCenter looks for a localized Help file, and then for an English one if a localized one is not found. If neither exist, WebCenter does not put a Help link on the page.

New style dynamic help system linked to help.esko.com

Since WebCenter 12.1, a lot of pages (mostly in the admin section) use a dynamic help system linked to help.esko.com. When a user clicks the help icon, context-aware help information is displayed. By default the documentation from help.esko.com is shown, but this behavior is customizable.

It is possible to customize a specific help topic, or to link a subset of help topics to a specific manual or page. The behavior of the help functionality can be configured in the custom folder on the Web Server.

Each help link has a topic (i.e. common/wc/reference/re_task). The topic of a help link can be found by looking at the link address: a help icon always links to help.jsp?topic={TOPIC}&lang={LANG}.

For customization, the following options are available:

- By placing html files in the correct location in the custom folder on the Web Server: Customization
 for help pages is done in the custom/help directory. Customization can be done per language (by
 adding files to custom/help/{LANG} directory (where {LANG} is the abbreviation for the language
 in WebCenter i.e. custom/help/en for English). Customization can also be done for all languages.
 This is done by putting files in custom/help/all.
- By adding a helpconfig.xml file with specific settings to the custom/help folder on the Web Server: This file can contain a set of rules that will be applied when no specific custom topic is found. In the custom help file you define rules that match topic names. When a rule matches, the rule is applied by sending the user to the correct location, defined in the rule.

Note:

The system first searches in the language specific custom folder for a customized html file, if no html file is found for a specific language, it will search in the custom/help/all folder for that topic.



14. Upgrading from WebCenter

You can upgrade directly to WebCenter 14 from older versions.

If you have an older version than 10.0, you will need to first upgrade to WebCenter 10.1 or 10.2, make sure it is running correctly, then upgrade to WebCenter 14.

14.1 Prepare for the Upgrade

Note:

This procedure **applies to all upgrade installations** for WebCenter 14 - even to "minor" updates between builds of the same version.

Note:

This procedure is fairly complex and involves direct manipulation of core application and database files.

Expert help is available to **perform the upgrade for you at a minimal cost**: contact your local Esko Customer Services division for a quote and scheduling.

For more detailed instructions than the brief overview provided in this document, please consult the main WebCenter Installation Guide on the installation media.

14.1.1 Prerequisites for the Upgrade

Installation Media and Licenses

Make sure you have the following at hand before proceeding:

Media

- WebCenter 14 DVD
- Automation Engine 14 DVD

Licenses

- ArtiosCAD 14.0en (FlexNet server license)
- WebCenter 14 (plus optionally Task Management, Advanced Approval, PDF download, Reporting, extra concurrent users)
- OBGE (On Board Graphics Engine)

Information Needed

Make sure you collect the following information:

- The location of the FileStore (you can find this information in C:\Artios\WebCenter\Config\appconfig.xml).
- The database engine to use (SQL Server 2008 (R2) / 2012 (Express Edition), Oracle 10g or Oracle 11g).

Note: If you are already using SQL Server 2005 or SQL Server 2005 Express Edition, you can continue using it. However, we recommend using SQL Server 2008 R2 or 2012 as it they more capacity.

- The name of the Database Server, the Oracle Database Identifier (SID) if using an Oracle database, and the database administrator password (sys password).
- The name and location of the WebCenter4_0 database instance (you can find this information in Artios\WebCenter\ApplicationServer\JBoss\server\default \deploy\wc5-ds.xml).
- Your Esko customer login and password for activating licenses.
- The IP address or name of the LDAP server and the port used for the secure connection (typically 636).

14.1.2 Prepare for the Upgrade on the Application Server

- 1. Copy the following onto the Application Server:
 - WebCenter 14 DVD
 - Automation Engine 14 DVD
 - ArtiosCAD 14.0en license
 - WebCenter 14 license (plus optional module licenses)
 - OBGE (On Board Graphics Engine) license
- 2. Back up:
 - the FileStore
 - the WebCenter4 0 database
 - the \Artios\WebCenter folder
 - the \Esko\Artios\WebCenter folder
 - any E-mail Notification customizations that may be stored in \WebCenter \ApplicationServer\EmailNotifications\Custom
 - all other non-standard customizations you may have implemented outside of the custom folders
- 3. Make a restore point for the OBGE.
- **4.** Make a backup of the server software configuration.

For detailed instructions on step 3 and 4, please refer to the **Automation Engine 14 Installation**Manual.

14.1.3 Prepare for the Upgrade on the Web Server

- 1. Copy the following onto the Web Server:
 - WebCenter 14 DVD



2. Back up \Artios\WebCenter and any non-standard customizations you have implemented outside of the WebCenter instances.

14.2 Upgrade WebCenter

14.2.1 Remove WebCenter

- 1. On the Application Server:
 - a) Remove the WebCenter software using the Add/Remove Programs applet in the Control Panel.
 - b) Reboot the server.
 - c) Using Windows Explorer, remove the \Artios\WebCenter and \Esko\Artios\WebCenter folders, and any other remaining WebCenter-related folders.

Note: Take care not to remove the FileStore if it is inside a WebCenter folder!

- 2. On the Web Server:
 - a) Remove the **WebCenter** software using the **Add/Remove Programs** applet in the **Control Panel**.
 - b) Reboot the Web Server.
 - c) Using IIS, remove all WebCenter instances (only the default "WebCenter_Inst" is removed automatically).
 - d) Using Windows Explorer, remove \Artios\WebCenter, and any other remaining WebCenter-related folders.

14.2.2 Install WebCenter 14

- **1.** On the Application Server, update ArtiosCAD to ArtiosCAD 14.0en, choosing the options described in *Install ArtiosCAD on the Application Server* on page 23 and the **Use the default configuration** upgrade option.
- 2. Upgrade the licence component using the Automation Engine 14 DVD:
 - a) Insert the Automation Engine 14 DVD.

If the DVD does not auto-start, double-click setup.exe in its root folder.

- b) In the window that opens, click English.
- c) Click either:
 - Software Installation in the main menu on the left of the window,
 - Proceed to the installation >> at the bottom of the window.
- d) Click Install on the next page.
- e) On the Instructions page, click Run the Automation Engine System Readiness Check.

At the end of the Readiness Check, read the resulting messages carefully. If the Readiness Check resulted in a problem, correct it before proceeding. Click **Exit** in the **Automation Engine 14 System Readiness Check** dialog when this is done.

- f) Click Install the License Server Components.
- g) Click Install the System Controller 1.0 and follow the instructions of the installation wizard.
- 3. Activate the Licenses on page 24.
- 4. Uninstall the old version of ArtiosCAD.
- **5.** Install WebCenter 14, using the English language installer, on the Application Server and on the Web Server, making use of the existing FileStore location and WebCenter4_0 database location.

Note: The installers in other languages should not be used, until further notice.

See Installing WebCenter on page 21 for more information on the installation procedure.

6. Install Certificates for LDAPS on the Application Server on page 55.

14.2.3 Upgrade the OBGE

Note:

- The OBGE must have the same or a later version than the Automation Engine production server.
- Make sure that you do not update any CADx component while updating the OBGE! CADx must only be updated by the ArtiosCAD installer.

Upgrade the OBGE (On-Board Graphic Engine) to Automation Engine 14:

- **1.** Upgrade the prerequisite components:
 - a) Insert the Automation Engine 14 DVD.

If the DVD does not auto-start, double-click setup.exe in its root folder.

- b) In the window that opens, click English.
- c) Click either:
 - Software Installation in the main menu on the left of the window,
 - Proceed to the installation >> at the bottom of the window.
- d) Click Install on the next page.
- e) Click **Install the prerequisite components** and follow the instructions of the installation wizard.

Note: Remember to not update any CADx component!

The prerequisite components are now upgraded.



2. Test the OBGE and check its configuration (Hot Folder and container, see *Configure the OBGE* on page 36 for details).

14.2.4 Configure WebCenter 14

- 1. If you had WebCenter customizations:
 - a) Reapply the email notification customization that you backed up in your custom folder.
 Mentions of an older version of WebCenter are automatically updated to "WebCenter 14".
 - b) Apply any standard customizations you saved earlier to your new WebCenter instance(s).
 - Redo any other non-standard customization that you may have had.
 See the WebCenter Customization guide for more information.



Attention:

- Do NOT copy the files as the XML structure might be different and you might break
 it
- Do not customize the **Default** instance of WebCenter as if it doesn't work anymore
 you will have to completely reinstall it!
- 2. In case running the database scripts automatically (preferred) is switched off, run the WebCenter 14 database scripts.
 - See *Run the Database Schema Scripts on the Application Server* on page 27 for more information on the database schema scripts.
- **3.** Log on the WebCenter web interface and change the administrator password (see *Log On to WebCenter and Change the Admin Password*).
- **4.** Deploy new WebCenter instances as desired. See *Deploying WebCenter* on page 64 for more information.

The upgrade is complete.

15. Uninstalling WebCenter

- 1. Log on to the Web Server as a member of the local Administrators group.
- 2. Stop the IIS Admin service.
- **3.** Backup all deployed sites within \Artios\WebCenter\WebServer\Tomcat\webapps in case they are needed in the future.
- **4.** Use the **Add/Remove Programs** applet in **Control Panel** to remove WebCenter.
- **5.** Manually delete all subdirectories under \Artios\WebCenter.
- 6. Log on to the Application Server as a member of the local Administrators group.
- 7. Back up \Artios\WebCenter\Filestore and all its subdirectories in case they are needed in the future.
- 8. Use the Add/Remove Programs applet in Control Panel to remove WebCenter.
- **9.** Manually delete all subdirectories under \Artios\WebCenter if you are intending to never again use WebCenter.
 - If WebCenter is uninstalled with the intention of installing a newer version (and keeping an existing database), do NOT delete the files in \Artios\WebCenter as they contain information needed for the new version to run with the existing admin password.
- **10.**If using Microsoft SQL Server 2005/2008, or Microsoft SQL Server 2005/2008 Express Edition, back up the WebCenter4_0 database and then use Enterprise Manager to manually delete the WebCenter4_0 database.
 - If using Oracle, backup the database and either delete the instance, or, if it is shared, connect to the instance and issue the <code>drop user webcenter cascade; command.</code>
- **11.**If the OBGE is installed, remove all the Esko products using the **Add/Remove Programs** applet in **Control Panel**. Select all products except the FLEXIm flexid drivers.
- **12.**Remove ArtiosCAD by using the **Add/Remove Programs** applet in **Control Panel**. Once all the products are removed, WebCenter should be completely removed.
- 13. Reboot your machine.